100-1006							
1000	United	States			Registrat	ion	OPP Identifier Number
<b>≎EP</b> A	Environmental P	rotection Ag	ency		Amendmei	nt	NOTIFICATION
	Washingtor	n, DC 20460		X	Other		
	An	plication for	Pesticide - Sec	tion	Ī		
1. Company/Product Number		101	2. EPA Produc			3. Pre	posed Classification
100-1006			George LaRoc	ca	•		`
Company/Product (Name)			PM#	-			Name Danking
DEMON® TO TERMITICAL	DE/INSECTICIDE		13				None Restricted
Name and Address of Applic		· · · · · · · · · · · · · · · · · · ·		Review	v. In accorda	nce with FIFF	RA Section 3(c)(3) (b)(i), my
Syngenta Crop Protection			product is similar o				
P. O. Box 18300 Greensboro, NC 27419	)		EPA Reg. No.				
	s a new <b>addre</b> ss		Product Name				
Chibox in Bird							
		Se	ction - II				Nome
Amendment - Explain be	low.			•		response to	NOTIFICATION
Resubmission in respons	se to Agency letter dated			• •	letter dated o" Application	ı.	AUG 2 0 2002
Notification - Explain belo	w.			Other -	Explain below	V.	
Explanation: Use additional	page(s) if necessary	v. (For Section	n I and Section II.)				
Syngenta Crop Protection is submimounds and fire ants.	itting 2 copies of labeling	with the addition	n of a California restri	ction (l	oy footnote) fo	or the followin	g pests: mole crickets, ant
This notification is consistent with							
the labeling or the confidential state statement to EPA. I further understatement							
violation of FIFRA and I may be su							
4 Banaini Thia Bundana (Billi	Do Donkowal III.	Sec	ction – III	<u></u>			
Material This Product Will Child-Resistant Packaging	Unit Packaging		Water Soluble Packa	aina	2.	Type of Cont	ainer
Yes*	Yes	<b>,</b>	Yes	J			etai
No	No		No				astic
*Certification must	If "Yes"	No. per If	Yes*	No. pe	r		ass per
be submitted	Unit Packaging wgt.			contair			her (Specify)
Location of Net Contents Info	rmation	4. Size(s) Ret	ail Container			cation of Labe	Directions
						On Label	
Label Cor	tainer					On Labelin	ng accompanying product
6. Manner in Which Label is Aff	ixed to Product [	Lithograp		$\Box$	Other		
		Paper glu Stenciled					
		Sec	tion – IV		······································		:
Contact Point (Complete iter	ns directly below for ider			if nec	essary, to pn		
Name John L. Hott		Title	e gulatory Product	Mar	ener	336-632	No. (Include Area Code)
JOHN E. HOU		Certification	galatory i roduci	17101	<u></u>	1 000-002	6. Date Application
I certify that the statements I I acknowledge that any knowl both under applicable law.						te.	૧૩cnived (Stamped)
Signature)	-, 42	3. Title		<del></del>			1
Col 1/1	li U	Regula	tory Product Ma	nage	Г		
4. Typed Name		5. Date					]
John L. Hott		August	9, 2002				

EPA Form 8570-1 (Rev. 8-94) Previous editions are obsolete.

#### Demon® TC

# Termiticide/Insecticide

For use by individuals/firms licensed or registered by the state to apply termiticide products. States may have more restrictive requirements regarding qualifications of persons using this product. Consult the structural pest control regulatory agency of your state prior to use of this product.

For control of termites and other listed arthropod pests.

**NOTIFICATION** 

AUG 2 0 2002

Active Ingredient:

Cypermethrin:1

 $(\pm)\alpha$ -cyano-(3-phenoxyphenyl)methyl $(\pm)$ -cis,trans-3-

Total: 100.0%

Contains petroleum distillates.

\*Cis/trans ratio: Min. 45% (±) cis and max. 55% (±) trans

Demon TC Insecticide contains 2 lbs. active ingredient per gal., formulated as an emulsifiable concentrate.

#### **KEEP OUT OF REACH OF CHILDREN**

#### WARNING/AVISO

Si usted no entiende la etiqueta, busque a alguien para que se la explique a usted en detalle. (If you do not understand the label, find someone to explain it to you in detail.)

See additional precautionary statements and directions for use inside booklet.

EPA Reg. No. 100-1006 EPA Est.

SCP 1006A-M1

U.S. Standard Measure

<sup>&</sup>lt;sup>1</sup>Pyrethroid Insecticide

	FIRST AID
If in eyes	<ul> <li>Hold eye open and rinse slowly and gently with water for 15-20 minutes.</li> <li>Remove contact lenses, if present, after the first 5 minutes, then continue rinsing eye.</li> <li>Call a poison control center or doctor for treatment advice.</li> </ul>
If on skin or clothing	<ul> <li>Take off contaminated clothing.</li> <li>Rinse skin immediately with plenty of water for 15-20 minutes.</li> <li>Call a poison control center or doctor for treatment advice.</li> </ul>
If swallowed	<ul> <li>Call a poison control center or doctor immediately for treatment advice.</li> <li>Do not give any liquid to the person.</li> <li>Do not induce vomiting unless told to do so by the poison control center or doctor.</li> <li>Do not give anything by mouth to an unconscious person.</li> </ul>
If inhaled	<ul> <li>Move person to fresh air.</li> <li>If person is not breathing, call 911 or an ambulance, then give artificial respiration, preferably by mouth-to-mouth, if possible.</li> <li>Call a poison control center or doctor for further treatment advice.</li> </ul>
	NOTE TO PHYSICIAN
	um distillate – vomiting may cause aspiration pneumonia
	t container or label with you when calling a poison control or going for treatment.
	HOT LINE NUMBER our Medical Emergency Assistance (Human or Animal) cal Emergency Assistance (Spill, Leak, Fire or Accident) Call 1-800-888-8372

# **PRECAUTIONARY STATEMENTS**

# **Hazards to Humans and Domestic Animals**

# WARNING

May be fatal if swallowed. Causes skin irritation. Harmful if absorbed through skin or inhaled. Causes moderate eye irritation. Prolonged or frequently repeated skin contact may cause allergic skin reactions in some individuals. Do not get on skin or on clothing.

Avoid contact with eyes. Avoid breathing vapors or spray mist. Wash thoroughly with soap and water after handling and before eating, drinking, or using tobacco. Remove and wash contaminated clothing before reuse.

# **Personal Protective Equipment**

All pesticide handlers (mixers, loaders, and applicators) must wear a chemical-resistant apron or long-sleeved coveralls worn over a minimum of short-sleeved shirt and short pants, socks, chemical-resistant footwear, chemical-resistant gloves. Regular work shirts, pants, socks, shoes and waterproof gloves are sufficient after the product is diluted in accordance with label directions for use and/or when mixing and loading using a closed spray tank transfer system, or an in-line injector system. In addition, all pesticide handlers must wear a respiratory protection device<sup>1</sup> when working in a non-ventilated space; all pesticide handlers must wear protective eyewear (goggles and/or faceshield and/or shielded safety glasses with front, brow and temple protection) when working in a non-ventilated space or when applying termiticide by rodding or sub-slab injection.

Use one of the following Mine Safety and Health Administration (MSHA)/National Institute for Occupational Safety and Health (NIOSH) respirator types with approval number prefixes or letters:

**TC-21C** (Dust/mist filtering respirator or a NIOSH approved respirator with a N, R, P or HE filter)

**TC-23C** (with an organic-vapor removing cartridge with pre-filter approved for pesticides), or

**TC-14G** (with an organic-vapor removing canister approved for pesticides), or a NIOSH approved respirator with an organic-vapor (OV) approved cartridge or canister with N, R, P or HE prefilter)

TC-19C (Supplied-air)

**TC-13F** (Self-contained breathing apparatus-SCBA)

When treating adjacent to an existing structure, the applicator must check the area to be treated, and immediately adjacent areas of the structure, for visible and accessible cracks and holes to prevent any leaks or significant exposures to persons occupying the structure. People present or residing in the structure during application must be advised to remove their pets and themselves from the structure if they see any signs of leakage. After application, the applicator is required to check for leaks. All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site. Do not allow people or pets to contact contaminated areas or to reoccupy contaminated areas of the structure until the clean up is completed.

#### **Environmental Hazards**

This pesticide is extremely toxic to fish. Use with care when applying in areas adjacent to any body of water. Do not apply directly to water, or to areas where surface water is present or to intertidal areas below the mean high water mark. Do not apply when weather conditions favor drift from treated areas. Do not contaminate water when cleaning equipment or disposing of equipment washwater.

This product is highly toxic to bees exposed to direct treatment or residues on crops or weeds. Do not apply Demon TC Insecticide, or allow it to drift to crops or weeds on which bees are actively foraging. Additional information may be obtained from your Cooperative Extension Service. Apply this product only as specified on this label.

For Treatment of Preconstruction Lumber and Logs: Do not discharge effluent containing this product into lakes, streams, ponds, estuaries, oceans, or other waters unless in accordance with the requirements of a National Pollutant Discharge Elimination System (NPDES) permit and the permitting authority has been notified in writing prior to discharge. Do not discharge effluent containing this product to sewer systems without previously notifying the local sewage treatment plant authority. For guidance contact your State Water Board or Regional Office of the EPA.

# **Physical and Chemical Hazards**

Do not use or store near heat or open flame.

# CONDITIONS OF SALE AND LIMITATION OF WARRANTY AND LIABILITY

**NOTICE:** Read the entire Directions for Use and Conditions of Sale and Limitation of Warranty and Liability before buying or using this product. If the terms are not acceptable, return the product at once, unopened, and the purchase price will be refunded.

The Directions for Use of this product should be followed carefully. It is impossible to eliminate all risks inherently associated with the use of this product. Ineffectiveness or other unintended consequences may result because of such factors as manner of use or application, weather, presence of other materials or other influencing factors in the use of the product, which are beyond the control of Syngenta Crop Protection, Inc. or Seller. All such risks shall be assumed by Buyer and User, and Buyer and User agree to hold Syngenta and Seller harmless for any claims relating to such factors.

Syngenta warrants that this product conforms to the chemical description on the label and is reasonably fit for the purposes stated in the Directions for Use, subject to the inherent risks referred to above, when used in accordance with directions under normal use conditions. This warranty does not extend to the use of this product contrary to label instructions, or under abnormal conditions or under conditions not reasonably foreseeable to or beyond the control of Seller or Syngenta, and Buyer and User assume the risk of any such use. SYNGENTA MAKES NO WARRANTIES OF MERCHANTABILITY OR OF FITNESS FOR A PARTICULAR PURPOSE NOR ANY OTHER EXPRESS OR IMPLIED WARRANTY EXCEPT AS STATED ABOVE.

In no event shall Syngenta or Seller be liable for any incidental, consequential or special damages resulting from the use or handling of this product. THE EXCLUSIVE REMEDY OF THE USER OR BUYER, AND THE EXCLUSIVE LIABILITY OF SYNGENTA AND SELLER FOR ANY AND ALL CLAIMS, LOSSES, INJURIES OR DAMAGES (INCLUDING CLAIMS BASED ON BREACH OF WARRANTY, CONTRACT, NEGLIGENCE, TORT, STRICT LIABILITY OR OTHERWISE) RESULTING FROM THE USE OR HANDLING OF THIS PRODUCT, SHALL BE THE RETURN OF THE PURCHASE PRICE OF THE PRODUCT OR, AT THE ELECTION OF SYNGENTA OR SELLER, THE REPLACEMENT OF THE PRODUCT.

Syngenta and Seller offer this product, and Buyer and User accept it, subject to the foregoing Conditions of Sale and Limitation of Warranty and Liability, which may not be modified except by written agreement signed by a duly authorized representative of Syngenta.

# **DIRECTIONS FOR USE**

It is a violation of Federal law to use this product in a manner inconsistent with its labeling.

Demon TC may be used on plants intended for aesthetic purposes or climate modification and being grown in interior plantscapes, ornamentals, gardens or parks, or lawns and grounds. Do not use in commercial greenhouses or nurseries. Not for use on plants or turf being grown for sale or other commercial use, or for commercial seed production, or for research purposes.

#### STORAGE AND DISPOSAL

## **Prohibitions**

Do not contaminate water, food or feed by storage or disposal. Open dumping is prohibited. Do not reuse empty container.

# Storage

Keep container closed when not in use. Do not store near food or feed. Protect from freezing. In case of spill or leak on floor or paved surfaces, soak up with sand, earth or synthetic absorbent. Remove to chemical waste area.

# Pesticide Disposal

Pesticide wastes are toxic. Improper disposal of excess pesticide, spray mixture or rinsate is a violation of Federal law. If these wastes cannot be disposed of by use according to label instructions, contact your State Pesticide or Environmental Control Agency, or the Hazardous Waste representative at the nearest EPA Regional Office for guidance.

# **Container Disposal**

#### **Metal Containers**

Triple rinse (or equivalent). Then offer for recycling or reconditioning, or puncture and dispose of in a sanitary landfill, or by other procedures approved by state and local authorities.

#### **Plastic Containers**

Triple rinse (or equivalent). Then offer for recycling or reconditioning, or puncture and dispose of in a sanitary landfill, or by other procedures allowed by state and local authorities.

#### **Refillable Return Containers**

Reseal container and offer for reconditioning, or triple rinse (or equivalent) and offer for recycling or reconditioning.

#### **Container Precautions**

Before refilling, inspect thoroughly for damage such as cracks, punctures, bulges, dents, abrasions, and damaged or worn threads on closure devices.

REFILL ONLY WITH Demon TC Insecticide. The contents of this container cannot be completely removed by cleaning. Refilling with materials other than Demon TC Insecticide will result in contamination and may weaken container.

After filling and before transporting, check for leaks.

Do not refill or transport damaged or leaking containers.

CONTAINER IS NOT SAFE FOR FOOD, FEED OR DRINKING WATER.

# GENERAL INFORMATION ON THE USE OF THIS PRODUCT FOR TERMITE CONTROL

Demon TC provides control of subterranean termites (including eastern subterranean, western subterranean, desert termite, and Formosan subterranean termite), and when applied to wood may be used for spot treatment of drywood termites (*Incisitermes* spp.).

Chemicals for soil treatment are used to establish a barrier against subterranean termite attack. The chemical emulsion must be adequately dispersed in the soil to provide a barrier between the wood in the structure and the termite colonies in the soil.

For the effective use of this product, it is necessary that the service technician be familiar with current control practices including trenching, rodding, subslab injection, and low-pressure spray applications. These techniques must be correctly employed to prevent or control infestations by subterranean termite species of *Reticulitermes*, *Zootermopsis*, *Heterotermes* and *Coptotermes* (Formosan termite). Choice of appropriate procedures should include consideration of such variable factors as the design of the structure, water table, soil type, soil compaction, grade conditions, location and type of domestic water supplies and drainage systems. The biology and behavior of the termite species involved are important factors to be known as well as suspected location of the colony and severity of the infestation within the structure to be protected.

Effective termite control also includes elimination of termite access to moisture by recommending repair of faulty construction grade and/or plumbing. Remove all wood and cellulose containing debris in contact with soil from crawl spaces, porches, and around foundations.

For advice concerning current control practices with relation to the specific local conditions, consult resources in structural pest control and the State regulatory agency.

EACH YEAR PRIOR TO AN APPLICATION TO VINYL SIDING, TREAT A SMALL AREA ON ALL SIDES OF THE STRUCTURE WHERE WEATHERING IS MOST SEVERE, AND ALLOW TO DRY. OBSERVE FOR STAINING. SOME TYPES OF VINYL SIDING, PARTICULARLY IF AGED OR WEATHERED, MAY SHOW SOME STAINING AFTER APPLICATION OF AN EMULSIFIABLE CONCENTRATE PRODUCT. TO COMPLETELY ELIMINATE THE POTENTIAL RISK ASSOCIATED WITH STAINING, IT IS SUGGESTED THAT A WATER BASED PRODUCT SUCH AS DEMAND CS BE USED.

# SUBTERRANEAN TERMITE CONTROL (Including Eastern, Western, and Formosan Termites)

#### **USE DIRECTIONS**

Apply a 0.25%-0.50% solution to establish subsurface termite control barriers as specified on product labeling.

Avoid contamination of public and private water supplies by following these precautions:

- Use anti-backflow equipment or procedures to prevent siphonage of pesticide back into water supplies.
- Do not treat soil beneath structures that contain wells or cisterns.
- Care must be taken to avoid runoff. Do not treat soil that is water-saturated or frozen. Do not treat while precipitation is occurring.
- Care should be taken that the treatment solution is not introduced into the gravel and/or pipe drainage system which may be located on the exterior of the foundation in close proximity to the footing of the structure.

Consult State and local specifications for recommended distance of treatment areas from wells. Refer to Federal Housing Administration Specifications for guidance on preconstruction treatments.

# **MIXING DIRECTIONS**

Mix the termiticide in the following manner:

- 1. Fill tank ¼ to ½ full with water.
- Start pump to begin by-pass agitation and place end of treating tool in tank to allow circulation through hose.
- 3. Add appropriate amount of Demon TC Insecticide.
- 4. Add remaining amount of water.
- 5. Let pump run and allow recirculation through the hose for 2-3 minutes.

# **Demon TC Use Dilutions**

				Tank	Size			
Concentration	1 Gal.		25 Gal.		50 Gal.		100 Gal.	
(% active)	Demon TC	Water	Demon TC	Water	Demon TC	Water	Demon TC	Water
0.25	1.3 oz.	126.7 oz.	32.0 oz.	24.8 gal.	0.5 gal.	49.5 gal.	1.0 gal.	99.0 gal.
0.5	2.6 oz.	125.4 oz.	64.0 oz.	24.5 gal.	1.0 gal.	49.0 gal.	2.0 gal.	98.0 gal.
1.0	5.1 oz.	122.0 oz.	128.0 oz.	24.0 gal.	2.0 gal.	48.0 gal.	4.0 gal.	96.0 gal.

#### **After Treatment**

All holes in commonly occupied areas into which material has been applied must be plugged. Plugs must be in a non-cellulose material or covered by an impervious, non-cellulose material.

#### **APPLICATION VOLUMES**

To provide maximum control and protection against termite infestation, apply the specified volume of the finished water emulsion and active ingredient as set forth in the directions for use section of this label. In situations which will not accept sufficient amounts of water, such as clay-rich soils, reduced volumes of emulsion can be used which will deliver the appropriate concentration of termiticide to the soil. This may also apply to sensitive areas and/or applications where less volume may be desirable. Under such circumstances, the volume may be reduced provided there is a corresponding increase in concentration so that the amount of active ingredient applied to the soil remains the same.

**Note:** Large reductions of application volume reduce the ability to obtain a continuous barrier. Variance is allowed when volume and concentration are consistent with label directed rates and a continuous barrier can still be achieved.

Where soil conditions will not accept application of specified volume (gallons) of emulsion, the 0.5% emulsion may be applied at one-half the labeled application volume or a 1% emulsion may be applied at one-half the labeled application volume. Distribute the treatment evenly.

**Note:** When volume is reduced, the hole spacing for subslab injection and soil rodding may require similar adjustments to account for lower volume dispersal of the termiticide in the soil. Volume adjustments at 1% are not recommended for subslab injection.

Volume Adjustment Chart		Rate (% Emulsion	on)
Volume Allowed	0.25%	0.5%	1.0%
Horizontal (gallons emulsion/10 ft.²)	1 gal.	0.5-1 gal.	0.25-0.5* gal
Vertical (gallons emulsion/10 lin. ft.)	4 gal.	2-4 gal.	1-2* gal.

<sup>\*</sup> Not recommended for subslab injection.

# PRECONSTRUCTION SUBTERRANEAN TERMITE TREATMENT

Effective preconstruction subterranean termite control requires the establishment of an unbroken vertical and/or horizontal chemical barrier between wood in the structure and the termite colonies in the soil.

Prior to each application, applicators must notify the general contractor, construction superintendent, or similar responsible party, of the intended termiticide application and intended sites of application and instruct the responsible person to notify construction workers and other individuals to leave the area to be treated during application and until the termiticide is absorbed into the soil.

To meet F.H.A. termite-proofing requirements, follow the latest edition of the Housing and Urban Development (H.U.D.) Minimum Property Standards.

# DO NOT APPLY AT A LOWER DOSAGE AND/OR CONCENTRATION THAN SPECIFIED ON THIS LABEL FOR APPLICATIONS PRIOR TO THE INSTALLATION OF THE FINISHED GRADE.

After grading is completed and prior to pouring of the slab, slab-supported or constructed porches, and other critical areas, make the following treatments:

#### HORIZONTAL BARRIERS

Horizontal barriers may be established in areas intended for covering such as floors, porches, and other critical areas, application shall be made by a low-pressure spray (less than 50 p.s.i. at the nozzle).

Apply the emulsion at the rate of 1 gal./10 sq. ft. to fill dirt. If fill is washed gravel or other coarse material, apply the emulsion at the rate of 1-1/2 gal./10 sq. ft. If concrete slabs cannot be poured over soil the same day it has been treated, a waterproof cover, such as polyethylene sheeting, should be placed over the soil. This is not necessary if foundation walls have been installed around the treated soil.

#### VERTICAL BARRIERS

Vertical barriers may be established around the base of foundations, plumbing, back-filled soil against foundation walls, and other critical areas; applications may be made by trenching and rodding into the trench or trenching. Apply the emulsion at the rate of 4 gal./10 lin. ft./ft. of depth. For example, a footing 3 ft. deep would require 12 gal. of emulsion/10 lin. ft.

When treating foundations deeper than 4 ft., apply the termiticide as the backfill is being replaced, or if the construction contractor fails to notify the applicator to permit this, treat the foundation to a minimum depth of 4 ft. after the backfill has been installed. The applicator must trench and rod into the trench or trench along the foundation walls and around pillars and other foundation elements, at the rate prescribed from grade to a minimum depth of 4 ft. When the top of the footing is exposed, the applicator must treat

the soil adjacent to the footing to a depth not to exceed the bottom of the footing. However, in no case should a structure be treated below the footing.

A trench need not be wider than 6 in. Rod from the base of a shallow trench to the top of the footings. Low-pressure spray (less than 50 p.s.i. at the nozzle) may be used to treat soil which will be replaced in the trench. Mix the emulsion with the soil as it is being replaced in the trench.

Soil should be treated around sewer lines, plumbing, or around any other utility extending from the soil through a slab.

#### HOLLOW MASONRY UNITS OF THE FOUNDATION

Drill and treat voids in multiple masonry elements of the structure extending from the structure to the soil in order to create a continuous treatment barrier in the area to be treated. Apply at the rate of 2 gal. of emulsion/10 lin. ft. of footing using a nozzle pressure of less than 25 p.s.i. When using this treatment access holes must be drilled below the sill plate and should be as close as possible to the footing as is practical. Treatment of voids in block or rubble foundation walls must be closely examined: Applicators must inspect areas of possible runoff as a precaution against application leakage in the treated areas. Some areas may not be treatable or may require mechanical alteration prior to treatment.

All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site. Do not allow people or pets to contact contaminated areas or to reoccupy the contaminated areas of the structure until the clean up is completed.

Not for use in voids insulated with rigid foam.

#### **CRAWL SPACES**

For crawl spaces apply at the rate of 4 gal. of emulsion/10 lin. ft./ft. of depth from grade to the top of the footing. Application may be made by trenching and rodding into the trench or trenching. If the footing is exposed at or above grade, application should be made with special care to avoid washout around footing. Treatment should include both sides of foundation and around all piers and pipes.

- Rod holes should be spaced to provide a continuous chemical barrier.
- Trench need not be wider than 6 in. nor below the foundation. The emulsion should be mixed with the soil as it is being replaced in the trench.

#### POSTCONSTRUCTION TREATMENTS

Postconstruction applications may be made by subslab injection, trenching and rodding into the trench or trenching using low-pressure spray not exceeding 25 p.s.i. at the nozzle.

For applications made after the final grade is installed, the applicator must trench and rod into the trench or trench along the foundation walls and around pillars and other foundation elements, at the rate prescribed from grade to the top of the footing. When the footing is more than 4 ft. below grade, the applicator must trench and rod into the trench or trench along the foundation walls at the rate prescribed to a minimum depth of 4 ft. The actual depth of treatment will vary depending on soil type, degree of compaction, and location of termite activity. When the top of the footing is exposed, the applicator must treat the soil adjacent to the footing to a depth not to exceed the bottom of the footing. However, in no case should a structure be treated below the footing.

Do not apply emulsion until location of heat or air-conditioning ducts, vents, and water and sewer (or plumbing) lines are known and identified. Caution must be taken to avoid contamination of these structural elements and airways.

#### **SLAB-ON-GROUND**

Apply the emulsion at the rate of 4 gal./10 lin. ft./ft. of depth. Application shall be made by sub-slab injection, trenching and rodding into the trench or trenching. Injectors should not extend below the tops of the footings.

Treat the soil from grade to the top of the footing along the outside and, where necessary, along the inside of the foundation perimeter. Treatment may also be required along one side of a partition wall (especially where the wall is connected to the flow by fixtures inserted in the slab) and along cracks, expansion joints, and other critical areas.

Drill holes should be spaced about 10-24 in. apart to provide a continuous chemical barrier. (For best results, application should be made with a lateral dispersion nozzle.)

Where necessary, drill through the foundation walls from the outside and inject the chemical just beneath the slab or along the inside of the foundation.

Along the outside of the foundation walls where shallow foundations exist (1 ft. or less), dig a narrow trench approximately 6 in. wide and not below the top of the footing. Apply the emulsion at the rate of 2 gal./10 lin. ft. As the soil is being replaced into the trench, apply another 2 gal./10 lin. ft. to the backfill.

When making soil applications to the foundations extending deeper than 1 ft., follow instructions under **BASEMENTS - Outside Perimeter**. (See exception for monolithic slabs immediately following.)

**Note:** For monolithic slab construction a vertical barrier may be established along the outside of foundation walls from grade to the bottom of the monolithic poured concrete foundation. Where the foundation extends deeper than 1 ft., rod holes should not extend beneath the bottom of the monolithic poured concrete foundation.

#### HOLLOW MASONRY UNITS OF FOUNDATION WALLS

Drill and treat voids in multiple masonry elements of the structure extending from the structure to the soil in order to create a continuous treatment barrier in the area to be treated. Apply at the rate of 2 gal. of emulsion/10 lin. ft. of footing using a nozzle pressure of less than 25 p.s.i. When using this treatment, access holes must be drilled below the sill plate and should be as close as possible to the footing as is practical. Treatment of voids in block or rubble foundation walls must be closely examined: applicators must inspect areas of possible runoff as a precaution against application leakage in the treated areas. Some areas may not be treatable or may require mechanical alteration prior to treatment.

All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site. Do not allow people or pets to contact contaminated areas or to reoccupy the contaminated areas of the structure until the clean up is completed.

Not for use in voids insulated with rigid foam.

When treating behind veneer, care should be taken not to drill beyond the veneer. If concrete blocks are behind the veneer, both the blocks and the veneer may be drilled and treated at the same time.

#### **BASEMENTS**

Apply the emulsion at the rate of 4 gal./10 lin. ft./ft. of depth from the grade to the top of the footing. For example a footing 3 ft. deep would require 12 gal. of emulsion/10 lin. ft. Application shall be made by subslab injection, trenching, and rodding into the trench or trenching.

#### Inside

Treatment may be required along inside of foundation walls and along one side of interior partition walls (or bearing walls) especially where the wall is connected by fixtures inserted in the floor. Application may also be necessary around sewer pipes, floor drains, conduits, or any cracks in the basement floor. Drill holes should be spaced about 10-24 in. apart to provide a continuous chemical barrier.

**Note:** Sandy soils will tend to give less lateral dispersion than clay soils. Spacing should be determined by soil type.

#### **Outside Perimeter**

Applications must be made by trenching and rodding into the trench or trenching. When rodding from grade or from the bottom of a shallow trench, rod holes should be spaced in a manner that will allow for application of a continuous chemical barrier. Rod holes should not extend beneath the top of the footings.

A trench need not be wider than 6 in. Rod from the base of a shallow trench to the top of the footings. Low-pressure spray (not exceeding 25 p.s.i.) may be used to treat soil which will be replaced in the trench. Mix the emulsion with the soil as it is being replaced in the trench.

HOLLOW MASONRY UNITS OF THE FOUNDATION AND/OR BASEMENT WALL (BELOW GRADE)

Treat so as to make a continuous chemical barrier in the voids. Apply the emulsion at the rate of 2 gal./10 lin. ft. Apply the emulsion so it will reach the footing.

# **ACCESSIBLE CRAWL SPACES**

For crawl spaces, apply vertical termiticide barriers at the rate of 4 gal. of emulsion/10 lin. ft./ft. of depth from grade to the top of the footing, or if the footing is more than 4 ft. below grade, to a minimum depth of 4 ft. Apply by trenching and rodding into the trench, or trenching. Treat both sides of foundation and around all piers and pipes. Where physical obstructions, such as concrete walkways adjacent to foundation elements, prevent trenching, treatment may be made by rodding alone. When soil type and/or conditions make trenching prohibitive, rodding may be used. When the top of the footing is exposed, the applicator must treat the soil adjacent to the footing to a depth not to exceed the bottom of the footing. Read and follow the mixing and use direction section of the label if situations are encountered where the soil will not accept the full application volume.

- Rod holes and trenches must not extend below the bottom of the footing.
- Rod holes must be spaced so as to achieve a continuous chemical barrier but in no case more than 12 in. apart.
- Trenches must be a minimum of 6 in. deep or to the bottom of the footing, whichever
  is less, and need not be wider than 6 in. When trenching in sloping (tiered) soil, the
  trench must be stepped to ensure adequate distribution and to prevent termiticide
  from running off. The emulsion must be mixed with the soil as it is replaced in the
  trench.
- When treating crawl spaces, turn off the air circulation system of the structure until application has been completed and all termiticide has been absorbed by the soil.

#### **INACCESSIBLE CRAWL SPACES**

For inaccessible interior areas, such as areas where there is insufficient clearance between floor joists and ground surfaces to allow operator access, excavate, if possible, and treat according to the instructions for accessible crawl spaces. Otherwise, apply one, or a combination of the following two methods.

To establish a horizontal barrier, apply to the soil surface, 1 gal. of emulsion/10 sq.
 ft. overall using a nozzle pressure of less than 25 p.s.i. and a coarse application



nozzle (e.g., Delavan Type RD Raindrop, RD-7 or larger, or Spraying Systems Co. 8010LP TeeJet or comparable nozzle). For an area that cannot be reached with the application wand, use one or more extension rods to make the application to the soil. Do not broadcast or powerspray with higher pressures.

 To establish a horizontal barrier, drill through the foundation wall or through the floor above and treat the soil perimeter at a rate of 1 gal. of emulsion/10 sq. ft. Drill spacing must be at intervals not to exceed 16 in. Many states have smaller intervals so check state regulations which may apply.

When treating crawl spaces, turn off the air circulation system of the structure until application has been completed and all termiticide has been absorbed by the soil.

It is recommended that inadequately ventilated crawl spaces be brought into compliance with FHA Minimum Property Standards specifying 1 sq. ft. of ventilator opening/150 sq. ft. of crawl space area.

**Note:** Children and pets should be kept out of treated area until surface is completely dry.

#### **BATH TRAPS**

Where there is exposed soil beneath and around plumbing/waste pipe entrances through a concrete slab, this soil may be treated with 0.5% dilution of this product.

An access door for inspection and treatment should be cut and installed if not already present. After inspection and removal of any wood (form boards) or cellular debris, treat the soil by rodding and/or drenching with 0.5% emulsion of this product.

#### **FOAM APPLICATIONS**

Demon TC Insecticide emulsion may be converted to a foam and the foam used to treat voids to control or prevent termite, ant, bee, wasp infestations or other arthropods harboring under slabs.

Depending on the circumstances, foam applications may be used alone or in combination with liquid emulsion applications. Applications may be made behind veneers, piers, chimney bases, into rubble foundations, into block voids or structural voids, under slabs, stoops, porches, or to the soil in crawlspaces, and other similar voids.

Foam and liquid application must be consistent with volume and active ingredient instructions in order to ensure proper application has been made. The volume and amount of active ingredient are essential to an effective treatment. At least 75% of the labeled liquid emulsion volume of product must be applied, with the remaining percent delivered to appropriate areas using foam application. Refer to label and use recommendations of the foam manufacturer and the foaming equipment manufacturer.

Foam applications are generally a good supplement to liquid treatments in difficult areas, but may be used alone in difficult spots.

Rates: Use a 0.25%-1.0% emulsion converted to a foam with expansion characteristics from 2-20 times.

**Note:** When using a foaming product be sure that it is compatible with Demon TC Insecticide.

# **Applications Under Slabs or to Soil in Crawl Spaces**

- Applications should be made using Demon TC Insecticide foam in combination with liquid emulsion applications.
- The total amount of product applied with the combination of foam and liquid emulsion should be equivalent to that of an application using a liquid emulsion only.

# **Applications to Other Areas**

- Applications may be made using either Demon TC Insecticide foam alone or in combination with a liquid emulsion.
- Applications may be made behind veneers, piers (concrete or wood), chimney bases, into rubble foundations, into block voids, structural voids (i.e., between stud walls), poles, stumps, and wood in crawl spaces.
- Applications may be made in other areas, which include but are not limited to:
  - Foundations penetrated by utility services,
  - Cracks and expansion joints.
  - Bath traps.
  - Areas where cement constructions have been poured adjacent to the foundation such as stairs, patios and slab additions.

# POSTS, POLES AND OTHER CONSTRUCTIONS

Application may be made to create a chemical barrier in the soil around wooden construction such as signs and landscape ornamentation by applying a 0.25-0.5% emulsion. Treat on all sides to create a continuous barrier around posts and poles.

Use 1 gal. of emulsion per ft. of depth for poles and posts less than 6 in. in diameter. For larger poles, use 1-1/2 gal. of emulsion./ft. of depth. For larger constructions, use 4 gal./10 lin. ft./ft. of depth.

For treatments made during installation, the emulsion may be applied to the soil as it is replaced around the pole or post. Previously installed poles and posts may be treated by subsurface injection or treated by gravity-flow through holes made from the bottom of a trench around the pole or post. Treat on all sides to create a continuous chemical barrier. Apply to a depth of 6 in. below the bottom of the wood.

Do not contaminate wells or cisterns.

#### STRUCTURES WITH WELLS/CISTERNS INSIDE FOUNDATIONS

Structures that contain wells or cisterns within the foundation of a structure can only be treated using the following techniques:

- 1. Do not treat soil while it is beneath or within the foundation or along the exterior perimeter of a structure that contains a well or cistern. The treated backfill method must be used if soil is removed and treated outside/away from the foundation. The treated backfill technique is described as follows:
  - (a) Trench and remove soil to be treated onto heavy plastic sheeting or similar material or into a wheelbarrow.
  - (b) Treat the soil at the rate of 4 gal. of dilute emulsion per 10 lin. ft./ft. of depth of the trench, or 1 gal. per 1.0 cu. ft. of soil. See "Mixing Directions" section of the label. Mix thoroughly into the soil taking care to contain the liquid and prevent runoff or spillage.
  - (c) After the treated soil has absorbed the diluted emulsion, replace the soil into the trench.
- Treat infested and/or damaged wood in place using an injection technique such as described in the TREATMENT OF WOOD IN PLACE FOR CONTROL OF TERMITES, CARPENTER ANTS, CARPENTER BEES AND WOOD INFESTING BEETLES section of this label.

# STRUCTURES WITH ADJACENT WELLS/CISTERNS AND/OR OTHER WATER BODIES

Applicators must inspect all structures with nearby water sources such as wells, cisterns, surface ponds, streams, and other bodies of water and evaluate, at a minimum, the treatment recommendations listed below prior to making an application.

- 1. Prior to treatment, if feasible, expose the water pipe(s) coming from the well to the structure, if the pipe(s) enter the structure within 3 ft. of grade.
- 2. Prior to treatment, applicators are advised to take precautions to limit the risk of applying the termiticide into subsurface drains that could empty into any bodies of water. These precautions include evaluating whether application of the termiticide to the top of the footer may result in contamination of the subsurface drain. Factors such as depth to the drain system and soil type and degree of compaction should be taken into account in determining the depth of treatment.
- 3. When appropriate (i.e., on the water side of the structure), the treated backfill technique (described above) can also be used to minimize off-site movement of termiticide.

#### **UNDERGROUND SERVICES**

Examples of underground services are wires, cables, utility lines, pipes and conduits. Services may be within structures or located outside structures, in right-of-ways or to protect long range (miles) or installations of services.

Soil treatment may be made using a 0.25%-0.5% Demon TC Insecticide emulsion to prevent attack by termites and ants.

Apply 2-4 gal. of emulsion/10 lin. ft. to the bottom of the trench and allow to soak into the soil. Lay services on the treated soil and cover with approximately 2 in. of fill soil. Apply another 2-4 gal./10 lin. ft. over the soil surface to complete the treatment barrier. In wide trenches, only treat the soil in the area near the service. It is important to establish a continuous barrier of treated soil surrounding the services.

Where soil conditions will not accept application of specified volume of 0.25% emulsion, the 0.5% emulsion may be applied at one-half the application rate or 2 gal./10 lin. ft.

Finish filling the trench with untreated fill soil. The soil where each service protrudes from the ground may be treated by trenching and rodding into the trench or trenching of no more than 1-2 gal. of emulsion into the soil.

Precaution: Do not treat electrically-active underground services.

# RETREATMENT

Retreatment for subterranean termites can only be performed if there is clear evidence of reinfestation or disruption of the barrier due to construction, excavation, or landscaping and/or evidence of the breakdown of the termiticide barrier in the soil. These vulnerable or reinfested areas may be retreated in accordance with application techniques described in this product's labeling. The timing and type of these retreatments will vary, depending on factors such as termite pressure, soil types, soil conditions and other factors which may reduce the effectiveness of the barrier.

Annual retreatment of the structure is prohibited unless there is clear evidence that reinfestation or barrier disruption has occurred.

# TREATMENT OF WOOD IN PLACE FOR CONTROL OF TERMITES, CARPENTER ANTS, CARPENTER BEES AND WOOD INFESTING BEETLES

In addition to subsurface applications, this product may be used for treating infested wood in place. It can be applied to wood by crack and crevice tool, coarse fan spray or injection. Overall broadcast spray applications must be limited to attics, crawl spaces, unfinished basements and similar generally unoccupied areas. In occupied indoor

2930

areas, treat wood trim and exposed beams by brush or coarse spray directed only onto the wood to be treated.

Use this spray at a rate of 1 gal. of diluted spray/1,000 sq. ft. of surface area.

**Important:** Do not apply emulsion until location of heat pipes, ducts, water and sewer lines and electrical conduits are known and identified. Caution must be taken to avoid puncturing and injection into these structural elements. Do not apply into electrical fixtures, switches, or sockets.

Remove pets, birds, and cover aquariums before spraying indoors. Do not permit humans or pets to contact treated surfaces until the spray has completely dried.

In the home, all food processing surfaces and utensils in the treatment area should be covered during treatment or thoroughly washed before reuse.

During any applications to overhead interior areas of structures, cover surfaces below with plastic sheeting or similar material.

#### **CONTROL OF WOOD INFESTING BEETLES**

To control wood infesting insects such as powderpost beetle (*Lyctidae*), false powderpost beetles (*Bostrichidae*), deathwatch beetles (*Anobiidae*), old house borers (*Cerambycidae*) and ambrosia beetles (*Scolytidae*) in homes and other structures, apply as an emulsion containing 0.25% Demon TC Insecticide. For treatment of small areas, apply by brushing the emulsion evenly on wood surfaces. For large or overhead areas, apply as a coarse spray. When spraying overhead interior areas of homes, apartment buildings, etc., cover all surfaces below the area being sprayed with plastic sheeting or other material which could be disposed of by placing in trash if contamination from dripping occurs. Sprayed surfaces should be avoided until spray has totally dried. Do not use in structures occupied by animals to be used for food purposes or which produce products for human consumption.

#### **TERMITES ABOVE GROUND**

For control of termites, subterranean aerial colonies, Formosan aerial colonies or drywood termites in localized areas of infested wood in structures, apply a 0.1%-0.25% emulsion to voids and galleries in damaged wood and in spaces between wooden members of a structure and between wood and foundations where wood is vulnerable. Application may be made to inaccessible areas by drilling, and then injecting the emulsion with a crack and crevice injector into the damaged wood or void spaces. Application to attics, crawl spaces unfinished basements, or man-made voids may be made with a coarse fan spray of 0.1%-0.25% emulsion to control workers and winged reproductive forms of termites in mud shelter tubes. This type of application is not intended to be a substitute for soil treatment of extensive infestation of drywood termites or other wood-infesting insects. Make treatments at a rate of 1 gal. of the emulsion/1,000 sq. ft. of surface area.

21/30

For termites active inside trees, utility poles and/or fence posts, drill to find the interior infested cavity and inject 0.1% emulsion using treatment tool with a splashback guard.

Termite carton nests in trees or building voids may be injected with 0.25%-0.50% emulsion using a pointed injection tool. Multiple injection points to varying depths may be necessary. It is desirable to physically remove carton nest material from building voids when such nests are found.

#### **CARPENTER ANTS**

For control of carpenter ants in houses and other structures, apply as a 0.25% emulsion for protection up to 5 weeks, a 0.5% emulsion for protection up to 11 weeks, and a 1.0% emulsion for protection up to 1 year, with retreatment semiannually as needed, around doors and windows and other places where carpenter ants enter the premises and where they crawl. Spray into cracks and crevices or through openings or small drilled holes into voids where these ants or their nests are present. Use no more than a sufficient amount of coarse spray to cover the area thoroughly, but not to the point of runoff. Do not exceed 1 gal. of dilute emulsion/1000 sq. ft. of treated surface.

For carpenter ants active inside trees, utility poles and/or fence posts, drill to find the interior infested cavity and inject 0.25% emulsion, for protection up to 1 week, using a treatment tool with a splashback guard. Reapply under heavy reinfestation pressure.

#### FIREWOOD PROTECTION FROM CARPENTER ANTS

Prior to laying in firewood, soil beneath the cord(s) may be treated with a 0.25%-0.50% emulsion at 1 gal./10 sq. ft. to prevent carpenter ant infestation.

#### CARPENTER BEES

Use a 0.1% emulsion for control of carpenter bees. Liquid may be sprayed directly into gallery entrance holes. Following treatment, the entrance holes may be left open 24 hrs. to be certain that returning adult bees are killed. When there is no activity, the hole may be closed with wood putty.

# Treatment of Preconstruction Lumber and Logs\*

To protect unseasoned lumber and logs from wood-destroying insects, such as termites, carpenter ants, and beetles (ambrosia, powder-post, old house borers, and others), totally treat wood with a 0.25% to 0.5% solution of Demon TC Insecticide. This solution can be applied by various methods, including spraying, brushing, dipping and pressure treatment. Frequent monitoring of dip and pressure systems are necessary to ensure that the desired level of Demon TC Insecticide is maintained. Wood can be handled after treatment when dry.

For dip treatments, the wood should be totally submersed in the solution until
thoroughly wet and then allowed to dry in a suitable location. Dipping solutions
to which Demon TC Insecticide has been added should be agitated before use if
left unused for long periods of time. Sediment, debris and other deposits should
be periodically cleaned from the tank.



- 2. For pressure treatments, the wood should be placed in the treatment chamber, the Demon TC Insecticide solution added, and the system pressurized up to 250 psi for up to 1 hour, depending on the density and type of wood treated. After the pressure is released and the system drained, the wood should be placed in a suitable location for drying.
- 3. For spray treatments, the wood should be sprayed thoroughly, including back and ends.
- 4. For brush treatments, all parts of wood surfaces should be thoroughly treated.

#### **GENERAL PEST CONTROL UNDER AND AROUND STRUCTURES**

Demon TC Insecticide may be diluted with water for use to control pests in and around homes and other structures. Pest controlled are listed in the following tables.

#### **UNDER SLABS**

Infestations of arthropods, such as ants, cockroaches and scorpions inhabiting under slab areas may be controlled by drilling and injecting or horizontal rodding and injecting, 1 gal. of 0.25%-0.5% emulsion/10 sq. ft. or 2 gal. of emulsion/10 lin. ft.

#### IN CRAWL SPACES

Broadcast Demon TC Insecticide at 0.25% to 0.5% to all surfaces in crawl spaces to control ants, fleas cockroaches, scorpions, or other arthropods. Product may also be applied through under-structure insecticidal delivery systems such as piping or flexible tubing mounted under the structure. This treatment is not intended as a substitute for termite control. Treat surfaces thoroughly, but not to point of runoff. Keep children and pets off surface until dry.

# **OUTSIDE SURFACES AND AROUND BUILDINGS**

Apply Demon TC Insecticide using a 0.1% emulsion as a residual treatment to outside surfaces of buildings including, but not limited to, exterior siding foundations, porches, window frames, eaves, patios, garages, refuse dumps, lawns or grass areas adjacent or around private homes, duplexes, townhouses, condominiums, house trailers, apartment complexes, carports, garages, fence lines, storage sheds, barns, and other residential structures, commercial, industrial and institutional buildings, soil, trunks of woody ornamentals and other areas where pests congregate or have been seen. Base need for retreatment upon monitoring for pest presence.

Keep children and pets off treated areas until completely dry.

#### CAUTION ON APPLICATION TO VINYL SIDING

EACH YEAR PRIOR TO AN APPLICATION TO VINYL SIDING, TREAT A SMALL AREA ON ALL SIDES OF THE STRUCTURE WHERE WEATHERING IS MOST SEVERE, AND ALLOW TO DRY. OBSERVE FOR STAINING. SOME TYPES OF VINYL SIDING, PARTICULARLY IF AGED OR

<sup>\*</sup>Not approved for use in California.

WEATHERED, MAY SHOW SOME STAINING AFTER APPLICATION OF AN EMULSIFIABLE CONCENTRATE PRODUCT. TO COMPLETELY ELIMINATE THE POTENTIAL RISK ASSOCIATED WITH STAINING, IT IS SUGGESTED THAT A WATER BASED PRODUCT SUCH AS DEMAND CS BE USED.

24/30

# BARRIER TREATMENT FOR PESTS AROUND STRUCTURES

Apply 0.1% to a band of soil and vegetation 6-10 ft. wide around and adjacent to the structure. Also, treat the foundation of the structure to a height of 2-3 ft. Use a treatment volume of 2-10 gal. per 1000 sq. ft. Higher volumes of water may be needed if mulch or leaf litter is present or dense foliage exists. House siding may be treated if boxelder bugs, elm leaf beetles, earwigs, silverfish or other similar pests are present.

Pest	Specific Instructions
Ants	Apply as a pinstream, as a fine/course, low
Bees	pressure spray (20 psi or less), as a spot
Carpenter Ants	treatment or with a paint brush. Treat where
Carpenter Bees	pests are found or entry points of the structure
Centipedes	such as windows and door frames and along the
Chiggers <sup>1</sup>	foundation.
Cockroaches	
Asian Cockroaches	
Crickets	
Earwigs	
Firebrats	
Flies	
Ground Beetles	
Mosquitoes	
Millipedes	
Pill Bugs <sup>1</sup>	
Scorpions	
Silverfish	
Sowbugs	
Spiders	
Wasps	

<sup>&</sup>lt;sup>1</sup>Not approved for use in California

# LAWN AND LANDSCAPE PEST CONTROL

Pest	Specific Instructions
Chinch Bugs <sup>1</sup> Mole Crickets <sup>1</sup>	For residential lawns, apply Demon TC Insecticide at the rate of 0.33-0.65 fl. oz. per 1000 ft.² in a volume of water sufficient for uniform coverage such as 3-20 gal. Use the lower rate to knock down pests and the higher rate where faster knockdown or greater residual is desired. Lawn should not be longer than 3 in. at the time of application. Base need for retreatment upon monitoring for pest presence. Application in combination with compatible surfactants may enhance penetration. Arid climates generally require the higher volume.
Ants Ant Mounds <sup>1</sup> Fire Ants <sup>1</sup>	Table.  Drench Method (Ant Mounds, Fire Ants): Apply 1-2 gal. of emulsion to each mound area by sprinkling the mound until it is wet and treat a 4 foot diameter circle around the mound. Use the higher volume for mounds larger than 12 in. For best results, apply in cool weather, such as in early morning or late evening hours, but not in the heat of the day.
Bark Beetles Borers Boxelder Bugs <sup>1</sup> Elm Leaf Beetles <sup>1</sup> Gypsy Moths (adults & caterpillars) <sup>1</sup>	Boxelder Bugs, Elm Leaf Beetles, Gypsy Moth Caterpillars: Spray tree trunks, building siding or wherever pests congregate, thoroughly, but not to the point of runoff.  Borers and Bark Beetles: To prevent infestation of trees and woody ornamentals, spray the bark, thoroughly, but not to the point of runoff.
Fleas & Ticks	Fleas and ticks: Mix 1.25-2.5 oz. of Demon TC Insecticide in 16-100 gal. of water and apply to 4000 sq. ft. of lawn. Use the lower rate to knock down existing fleas and the higher rate where faster knockdown or greater residual is desired.

<sup>&</sup>lt;sup>1</sup>Not approved for use in California

# LAWN APPLICATION DILUTION TABLE: Demon TC rate (oz.) for 100 gal. according to volume of application.

Example: For a Chinch bug application at the rate of 0.65 oz. per 1000 ft<sup>2</sup>, using 5 gal. of solution per 1000 sq. ft. of lawn, use 13 oz. of Demon TC in a 100 gal. tank. (1 fl. oz. equals 30 ml.).

Volume per 1000 ft <sup>2</sup>	Amount of Demon TC					
	0.33 oz./ 1000 ft. <sup>2</sup>	0.5 oz./ 1000 ft. <sup>2</sup>	0.65 oz./ 1000 ft. <sup>2</sup>			
5 gal.	6.5 oz.	10.0 oz.	13.0 oz.			
8 gal.	4.0 oz.	6.5 oz.	8.0 oz.			
10 gal.	3.5 oz.	5.0 oz.	6.5 oz.			
15 gal.	2.0 oz.	3.5 oz.	4.5 oz.			
20 gal.	1.5 oz.	2.5 oz.	3.5 oz.			

# **GENERAL RESTRICTIONS AND PRECAUTIONS**

Do not use in food or feed areas of food handling establishments, restaurants or other areas where food or feed is commercially prepared or processed. Do not use in serving areas while food is exposed or facility is in operation. Serving areas are areas where prepared foods are served such as dining rooms but excluding areas where food may be prepared or held.

Nonfood/feed areas are areas such as garbage rooms, lavatories, floor drains (to sewers), entries and vestibules, offices, locker rooms, machine rooms, boiler rooms, garages, mop closets and storage (after canning or bottling).

Not for use in USDA meat and poultry plants.

# DO NOT APPLY THIS PRODUCT TO EDIBLE CROPS.

Do not use in warehouses where raw or cured tobacco is stored.

Do not use in warehouses while raw agricultural commodities for food or feed are being stored.

Thoroughly wash dishes and food handling utensils with soap and water if they become contaminated by application of this product.

Do not allow spray to contact food, food stuffs, food contacting surface, food utensils or water supplies.

Do not apply to pets, crops or sources of electricity.

Do not allow people or pets on treated surfaces until the spray has completely dried.

28/30

Do not use concentrate or emulsion in fogging equipment.

During indoor surface application, do not allow dripping or run-off to occur.

Do not apply this product in any rooms being used as living, eating, sleeping or recovery area by patients, the elderly or infirm when they are in the room.

Do not apply to classrooms when in use.

Do not touch treated surface until dry.

Demon® and the Syngenta logo are trademarks of a Syngenta Group Company U.S. Patent No. 4,024,163

©2002 Syngenta

For non-emergency (e.g., current product information) call Syngenta Crop Protection at 1-800-334-9481

Syngenta Crop Protection, Inc. Greensboro, North Carolina 27409 www.syngenta-us.com

SCP 1006A-M1

Z:LABELD-W/DEMONTC1006A-M-lg-8/02/02

#### Chron

9/7/01 – Updated with language approved 7/9/01 – First Aid, pre construction statements, mixing table & dilution table.

12/10/01 – Revised First Aid per PR Notice 2001-1; revised container disposal statement; added staining statement; Syngenta format; made technical word changes per professional products technical specialist.

4/19/02 - Revised per EPA letter of 4/10/02.

6/21/02 – Revised Environmental Hazard section to include "Preconstruction Lumber and Log Treatment" statement per EPA acceptance letter of 6/21/02.

6/26/02 - Added Spanish signal word and precautionary statement to first page. Corrected reference to a section to be consistent with heading.

8/2/02 - Added California restriction to mole crickets, ant mounds, and fire ants.

Syngenta Crop Protection, Inc. Tel 336 632 6000 P.O. Box 18300 Greensboro, NC 27419-8300 www.syngenta.com

# syngenta

August 9, 2002

Document Processing Desk (NOTIF) Office of Pesticide Programs (H7504C) U.S. Environmental Protection Agency Room 266A, Crystal Mall 1921 Jefferson Davis Highway Arlington, VA 22202-4501

SUBJECT:

DEMON® TC TERMITICIDE/INSECTICIDE; EPA REG. NO. 100-1006; NOTIFICATION OF ADDITION OF CALIFORNIA RESTRICTION FOR CERTAIN PESTS

Dear Ms. Hobgood,

Syngenta Crop Protection is submitting 2 copies of labeling with the addition of a California restriction (by footnote) for the following pests: mole crickets, ant mounds and fire ants.

The label code is SCP 1006A-M1 (dated 08/02/02 on the last page of the label).

If you have any questions please contact me at (336) 632-7096.

Sincerely,

John L. Hott, Ph.D.

Regulatory Product Manager

Regulatory Affairs

Enclosures:

2 copies of final printed label (1 highlighted with changes)

EPA 8570-1 Form