

working properly. Avoid concentration of the material in narrow bands.

Do not apply TREFLAN granules by aerial application.

#### INCORPORATION DIRECTIONS

Incorporate TREFLAN one time within 24 hours after application. The second incorporation should be performed in the spring prior to seeding flax. The incorporation operations should result in a thorough mixing of TREFLAN with the soil. Otherwise, erratic weed control may result.

#### INCORPORATION EQUIPMENT

Use machinery that mixes TREFLAN thoroughly with the soil. Recommended equipment includes:

Disc - set to cut 3-4 inches deep and operated in 2 different directions at 4 to 6 mph. A tandem or double-disc operated one time does not provide adequate incorporation.

Field cultivator - set to cut 3 to 4 inches deep and operated at 5 mph or more. The field cultivator used alone or in combination with the double-disc will provide effective incorporation providing the following instructions are used:

1. Two passes over the field with a field cultivator with second pass running at an angle to the first. Do not set cultivator to cut deeper than 4 inches. Be sure a depth of not greater than 4 inches is maintained on the second pass since untreated soil may be turned up.
2. Field cultivator used for the first pass and the double-disc used for the second pass.
3. Double-disc used for the first pass and the field cultivator used for the second pass.

NOTE: A field cultivator is defined as an implement with 3 to 4 rows of sweeps spaced at intervals of 7 inches or less and staggered so that no soil is left unturned. Chisel points should not be used.

Mulch breeder and other similar disc-type implements - set to cut 3 to 4 inches deep and operated at 5 to 8 mph in two different directions.

BEST AVAILABLE

SPECIAL INSTRUCTIONS FOR FLAX

1. Incorporation operations or any other tillages performed in the spring prior to seeding should be relatively shallow so as to maintain a firm seedbed and the seedbed should be packed just prior to seeding.
2. Seeding may be done with either a press drill or a hoe drill and should be made into a moist seedbed no more than 1 1/2 inches deep.
3. Flax should not be seeded until the seedbed has warmed up.
4. Refer to the special precautions statement on the TREFLAN label regarding stresses that can lead to crop injury or yield reduction.

NOTE: Do not delay the first incorporation more than 24 hours after application.

**WARNING**

Refer to the TREFLAN label for additional warnings, cautions, precautions, and special precautions before use.

TREFLAN<sup>®</sup> (trifluralin), Elanco Products Company

ELANCO PRODUCTS COMPANY  
A Division of Eli Lilly and Company  
Indianapolis, Indiana 46285

tr/2315P  
07/09/81