

POTATOES (Whole or Cut Pieces)	At planting, dragoff or layby	6-14 lbs. per acre depending on soil type and weeds to be controlled (See Section above on Rates of Application and Weeds Controlled).	Apply uniformly to the soil as a spray at planting or if the top of the beds are to be dragged off. DCPA should be applied after dragoff. Layby application can be made up to 5 weeks after planting. If weeds have emerged at layby, the crop should be weeded or cultivated prior to application. Pre-plant soil incorporation not recommended.
SWEET POTATOES and YAMS	At transplanting and layby.	"	Apply uniformly to the soil as a spray at transplanting. DCPA can be sprayed directly over transplants without injury. Layby application can be made up to 6 weeks after transplanting.
TOMATOES	4-6 weeks after transplanting	"	Application uniformly to the soil should be confined to a period of 4-6 weeks after transplanting. DCPA 75W can be sprayed directly over the transplants without injury. If weeds have emerged, the crop should be cultivated or weeded prior to making the DCPA application.
EGGPLANT & PEPPERS	At transplanting and layby.	"	Apply uniformly to the soil as a spray at transplanting. DCPA can be sprayed directly over transplants without injury. Lay application can be made up to 6 weeks after planting. If weeds are present, the crop should be weeded or cultivated prior to making the layby application.
STRAWBERRIES New Plantings	At transplanting	12 pounds per acre	Apply uniformly to the soil as a spray. For new beds, apply 12 pounds at transplanting. Application of 8-12 pounds per acre may be applied to control late summer or early fall germinating weeds. Application to established plantings should be made in fall and early spring. Do not apply after first bloom. These applications may be made without injury.
Established Plantings	Fall and early spring	8-12 lbs. per acre	
COTTON	At seeding and layby. Surface or soil incorporated	6-10 pounds per acre	Apply uniformly to the soil at time of planting. Higher rates of 10-14 pounds are recommended for areas under irrigation. Layby application at 6-10 pounds can be made but not after bolls open. If weeds are present, the cotton should be weeded or cultivated prior to making the layby application.
CORN	At seeding	6-14 pounds per acre depending on soil type & weeds to be controlled (See section above on Rates of Application and Weeds Controlled).	Apply uniformly to the soil at time of planting. Rates of 10-14 pounds DCPA should be used on heavier soils. DO NOT INCORPORATE into soil. Where possible, irrigate after treating, for best results.