

8133-32

12/7/2006

115

PRECAUTIONARY STATEMENTS DANGER

HAZARDS TO HUMANS AND DOMESTIC ANIMALS

Corrosive. Causes eye damage and skin irritation. Methanol may cause blindness. Harmful or fatal if swallowed. **DO NOT** get in eyes, on skin or on clothing. Avoid contamination of food. Wash thoroughly with soap and water after handling. Remove contaminated clothing and wash before reuse. Vapors harmful. Avoid breathing spray, mist or vapors. Wear a NIOSH/MSHA respirator approved for formaldehyde exposure, chemical resistant boots or shoe covers, chemical resistant gloves and goggles (if a full face respirator is not used) when handling.

Formaldehyde is a primary skin sensitizing agent which may cause allergic contact dermatitis. Inhalation studies in test animals have produced an excess of tumors. Users should consider the possibility that overexposure to the active ingredient may pose a cancer risk. Formaldehyde is considered an occupational carcinogen by OSHA and users should be aware of the occupational exposure standard PEL (Permissible Exposure Limit) of 0.75 ppm.

ENVIRONMENTAL HAZARDS

This pesticide is toxic to fish. **DO NOT** discharge effluent containing this active ingredient into lakes, streams, ponds, estuaries, oceans, or other waters unless in accordance with the requirements of a National Pollutant Discharge Elimination System (NPDES) permit and the permitting authority has been notified in writing prior to discharge. **DO NOT** discharge effluent containing this product into sewer systems without previously notifying the local sewage treatment plant authority. For guidance contact your State Water Board or Regional Office of the EPA.

PHYSICAL AND CHEMICAL HAZARDS

Do not use or store near heat or open flames.

IN CASE OF FIRE: Use CO₂ or dry chemical for small fires, alcohol type aqueous film forming foam or water spray for large fires. Use water spray to cool fire exposed containers. Wear self-contained breathing apparatus and complete personal protective equipment when potential for exposure to vapors or products of combustion exists.

IN CASE OF SPILL: Clean up immediately. Place leaking containers in well ventilated area. Eliminate ignition sources. To clean up spills, flush area sparingly with water or use absorbent. Avoid run-off to storm sewers and ditches leading to natural waterways. Neutralize with ammonium hydroxide or sodium hydroxide.

Do not allow access to treated areas by any person unless provided with a respirator approved by NIOSH/MSHA for formaldehyde exposure unless the formaldehyde vapor level has been determined to be below 0.75 PPM. Warning signs may be removed only after the vapor level drops below 0.75 PPM as determined by an OSHA approved method used in accordance with the manufacturer's instructions.

MONITORING OF PERSONNEL - In accordance with Formaldehyde regulation 29 CFR Section 1910.1048, all personnel who transport, pour, apply and clean-up Formaldehyde must monitor Formaldehyde in order to insure workplace safety. The Formaldehyde vapor level must be measured to be below 0.75 ppm, using a PEL (8 hour) monitor that meets the NIOSH method 3500, following the manufacturer's instructions. All personnel that transport, pour, apply and clean up Formaldehyde must monitor peak exposure to Formaldehyde at below 2.0 ppm with a STEL (15 minute) monitor that meets the NIOSH method 3500, in accordance with the manufacturer's directions. PEL monitors are to be worn throughout the workshift. STEL monitors are to be worn for 15 minutes during the time of potential peak exposure.

Shipping USA: Formaldehyde Solutions, 8, UN2209, PGIII, RQ
#2076 (10/06)

FORMALDEHYDE SOLUTION 37 MICROBIOCIDES

FOR USE IN HATCHERIES AS A FUMIGANT. FOR USE IN POULTRY AND SWINE CONFINEMENT BUILDINGS, MUSHROOM HOUSES, CITRUS FACILITIES, AND FOR USE IN DISINFECTING AND FUMIGATING ROOMS AND RAILROAD CARS. FOR USE BY FORMULATORS IN PREPARATION OF FORMULATED PRODUCTS.

Active Ingredient:	
Formaldehyde.....	37.0%
Other Ingredients.....	63.0%
Total	100.0%

(Contains methanol)

KEEP OUT OF REACH OF CHILDREN



**DANGER/PELIGRO
POISON**



Si usted no entiende la etiqueta, busque a alguien para que se la explique a usted a detalle (If you do not understand the label, find someone to explain it to you in detail.)

POTENTIAL CANCER HAZARD based on animal data and limited epidemiological evidence. May cause allergic skin reaction, reproductive disorders, lung damage, liver damage, kidney damage, brain and nervous system damage.

FIRST AID

IF INHALED: Move victim to fresh air. If not breathing, call 911 or an ambulance, then, give artificial respiration, preferably mouth-to-mouth if possible. Call a poison control center or doctor for further treatment advice.

IF IN EYES: Hold eyes open. Rinse slowly with water for 15-20 minutes. Remove contact lenses, if present after first 5 minutes, then, continue rinsing eye. Call a poison control center or doctor for treatment advice.

IF ON SKIN OR CLOTHING: Take off contaminated clothing. Rinse skin immediately with plenty of water for at least 15 to 20 minutes. Call a poison control center or doctor for treatment advice.

IF SWALLOWED: Call a poison control center or doctor immediately for treatment advice. Have person sip a glass of water if able to swallow. Do not induce vomiting unless told to do so by a poison control center. Do not give anything by mouth to an unconscious person.

Note to Physician: Probable mucosal damage may contraindicate the use of gastric lavage.

SEE LEFT SIDE PANEL FOR ADDITIONAL PRECAUTIONARY STATEMENTS



Champion Technologies, Inc.
P.O. Box 450499
Houston, Texas 77245

EPA REG. No. 8133-32	EPA EST. No.	8785-CA-001
		8785-NC-001
		8785-AL-001

Net Weight (lbs)	480
Net Content (US gals)	53

IN-CONTAINER PRESERVATIVE

FORMALDEHYDE SOLUTION 37 is recommended as an in-container preservative for industrial and household consumer products such as air fresheners, automotive products, fabric softeners, hand cleaners, polishes for floors and furniture, shoe polishes, moist sponges, and towelettes, spray starch, waxes and automotive polishes, hand and automatic dish detergents, liquid laundry detergents and car washes, household cleaners, industrial cleaners, liquid hand soaps, oil and grease removers, carpet cleaners and spot removers, waterless hand cleaners, raw materials for cleaning products, surfactants and silicone emulsions.

Formulators are responsible for obtaining FDA clearance for their formulated products in pulp and paper products and coatings that may come in contact with food.

FORMALDEHYDE SOLUTION 37 may not be used in products coming in direct contact with food and/or drinking water.

STORAGE AND DISPOSAL

STORAGE: Do not contaminate water, food or feed by storage or disposal. Should be stored apart from other combustibles, acids or oxidizing agents. Storage facilities should be non-combustible.

- Keep away from lights, fire and sparks.
- Keep closure up to prevent leaking.
- Make certain closure is securely closed before moving.
- Keep container closed.
- Loosen closure carefully.
- Keep out of sun and away from heat.
- Store in a cool place.
- Never use pressure to empty.
- Ground container before emptying.
- Always handle in upright position.
- Never roll a container.
- Never add other material to container.

PESTICIDE DISPOSAL: Do not contaminate water, food or feed by disposal. Pesticide wastes are toxic. Improper disposal of excess pesticide spray mixture or rinsate is a violation of Federal law. If these wastes cannot be disposed of according to label instructions, contact your State Pesticide or Environmental Control Agency, or Hazard Waste representative at nearest EPA Regional Office for guidance.

CONTAINER DISPOSAL: Completely empty drum, then, dispose of empty drum in accordance with Federal, State or Local regulations. After this container has been emptied, it may contain explosive vapors. Keep away from heat, sparks, and flames. Do not cut, puncture, or weld on or near this container when empty.

SPILL CLEAN UP REQUIREMENTS: Should a spill occur, contaminated soil and other clean up debris is a hazardous waste. If a reportable quantity is exceeded, report spill/leak to the National Response Center (800-424-8802). Reportable quantity (RQ) for formaldehyde is 100 pounds.

PHYSICAL PROPERTIES

Specific Gravity.....	1.08	Solubility in Water @ 20°C....	Complete
Pounds Per Gallon.....	9.00	Flash Point	≥140 °F
Vapor Pressure.....	40 mmHg	pH	3.5 - 4.5

Health	3
Fire	2
Reactivity	1
Personal Protection	*

AGRICULTURAL WORKER SAFETY USE REQUIREMENTS

Use this product only in accordance with its labeling and with the Worker Protection Standard, 40 CFR 170. This standard contains requirements for the protection of agricultural workers on farms, forests, nurseries, and greenhouses, and handlers of agricultural pesticides. It contains requirements for training, decontamination, notification, and emergency assistance. It also contains specific instructions and exceptions pertaining to the statements in this labeling about personal protective equipment, restricted-entry intervals, and notification to workers. These requirements only apply to uses of this product that are covered by the Worker Protection Standard (WPS).

Do not apply this product in a way that will contact workers or other persons, either directly or through drift. Only protected handlers may be in the area during application. For any requirements specific to your State or Tribe, consult the Agency responsible for Pesticide Regulation.

Entry Restrictions: Follow the applicable entry restrictions listed elsewhere on the product labeling.

Notification Instructions: Follow the rules in the WPS for notifying workers of the application.

Exception: If there are instructions elsewhere on the product labeling that requires the posting of specific signs at treated areas, you must notify workers of the application by warning them orally AND by posting the signs specified on the labeling.

Personal Protective Equipment (PPE) Requirements:

Handler PPE: Applicators and other handlers must wear:

Air purifying full-face respirator with formaldehyde cartridges if in area being treated. Coveralls over long-sleeved shirt & long pants. Chemical resistant gloves such as barrier laminate or vitron. Chemical resistant footwear plus socks. Protective eyewear, and chemical resistant headgear for overhead exposure. Chemical resistant apron when cleaning equipment, mixing or loading.

Early Entry PPE required for early entry to treated areas that is permitted under Worker Protection Standard and that involves contact with anything that has been treated, such as plants, soil, or water is:

Air purifying full-face respirator with formaldehyde cartridges. Coveralls over long-sleeved shirt & long pants. Chemical resistant gloves such as barrier laminate or vitron. Chemical resistant footwear plus socks. Protective eyewear, and chemical resistant headgear for overhead exposure.


Conflicting Instructions: If the requirements of the WPS conflict with instructions listed elsewhere on this product label, users must obey the more protective requirements.

CHEMICAL EMERGENCY CALL CHAMPION TECHNOLOGIES, INC. AT 281-431-2561 OR CHEMTREC AT 1-800-424-9300

BEFORE USING CONSULT MATERIAL SAFETY DATA SHEET

To request a Material Safety Data Sheet, please call 281-431-2561 or write Champion Technologies, Inc., P.O. Box 450499, Houston, TX 77245-0499

Champion Technologies, Inc. assumes no responsibility when this product is not used in accordance with the instructions contained on this label.



DIRECTIONS FOR USE

It is a violation of Federal law to use this product in a manner inconsistent with its labeling.

SEE SIDE PANELS FOR ADDED DIRECTIONS FOR USE.

AGRICULTURAL USES: Prior to all housing applications, warning signs must be posted on confinement buildings as specified in State, Local and Federal Regulations. Where required, trained personnel must be present during introduction of the **FORMALDEHYDE SOLUTION 37**.

FOR DISINFECTING AND FUMIGATING ROOMS, RAILWAY CARS: For each 1,000 cubic feet of space to be fumigated, use 16 1/2 oz. Potassium Permanganate and 20 oz. **FORMALDEHYDE SOLUTION 37**. Place on floor, a large dishpan in which a smaller pan is set. Put Potassium Permanganate into smaller pan and pour **FORMALDEHYDE SOLUTION 37** over it. Leave room immediately, closing tightly for about five hours, then, ventilate. Room may be reentered when level of formaldehyde is below 0.75 ppm as determined by an OSHA approved method used in accordance with manufacturer's instructions.

FOR FUMIGATION OF HATCHING EGGS: Incubators may be fumigated using a maximum of 1 fl. oz. of **FORMALDEHYDE SOLUTION 37** for each 30 cu. ft. of space. Manufacturer's information should be consulted for the area of a particular incubator. Dilute solution is to be placed in an open container and allowed to naturally evaporate. Potassium permanganate should not be used as a catalyst to liberate formaldehyde gas. Fumigation may be performed on both empty incubators and incubators containing eggs. Incubator hatcheries must be vented directly to outside air. Room housing the incubator hatchery should also have adequate ventilation. Warning signs must be placed on incubator hatchery and in surrounding area before fumigation may begin.

Eggs to be fumigated should be held on clean racks or egg flats which permit air circulation. Fumigation is most effective if applied to nest clean eggs as soon after collection as possible or when eggs are delivered to the hatchery or when set in incubator. Fumigation of eggs should not be done between 24 hours and five (5) days incubation because embryo damage may occur at this time.

Fumigation procedure may be repeated at 24-hour intervals up to 19th day of incubation. If fumigation is to be continued after 19th day, amount of **FORMALDEHYDE SOLUTION 37** normally used must be reduced by 50% (1/2 fl. oz. / 30 cu. ft.). Last application of formaldehyde solution should be added at least 12 hours before chicks are pulled to allow time for its complete evaporation. General access to the area may be allowed, and warning signs may be removed, when sufficient aeration has occurred to reduce formaldehyde vapor level to below 0.75 ppm as determined by an OSHA approved method used in accordance with manufacturer's instructions.

FOR USE IN FUMIGATION OF POULTRY AND SWINE CONFINEMENT BUILDINGS: **FORMALDEHYDE SOLUTION 37** can only be applied to unoccupied poultry and swine confinement buildings by either spray sled method or fixed sprinkler method. No workers are permitted in treated building during treatment. All application methods must be carried out and controlled from outside the area being fumigated.

For Poultry or Swine Confinement Buildings: Remove all poultry or swine and feed from premises to assure adequate surface coverage. Remove all portable equipment. Remove all bedding, manure and debris. Clean all appropriate surfaces. Empty all water troughs and feed racks. Clean rinse all surfaces with water. Sanitize with a suitable and approved sanitizing solution.

Posting: Post warning signs on confinement building prior to start of fumigation. Post signs in plainly visible locations on or in immediate vicinity of all entrances. Do not remove signs until fumigation, ventilation and final testing has been completed, and building is safe for reentering. Warning signs shall be printed in red on white background and shall contain, in English and Spanish, the following statement in letters not less than two inches in height: "DANGER-FUMIGATION". They shall also depict a skull and crossbones not less than one inch in height and shall state in letters not less than one-half inch in height "FORMALDEHYDE" date and time fumigant was introduced, and name, address and telephone number of the applicator performing the fumigation.

Trained personnel must be present during the introduction of **FORMALDEHYDE SOLUTION 37** and, after 24-hour treatment period, if entry is necessary into treated confinement building for purposes of facilitating aeration. Establish prohibited entry zones extending at least 25 feet from building wherever aeration of fumigant is accomplished by opening doors or windows in areas where workers may be present. Identify prohibited entry zones with cones and yellow cautionary tape, staked 3 to 4 feet off the ground, using posting signs as described above.

Mixing/Loading Instructions for remote house application methods: Calculate volume of building to be treated. Use 20 - 60 fluid ounces (590 - 1770 mL) **FORMALDEHYDE SOLUTION 37** for each 1000 cubic feet of building volume. **Dilution:** See specific dilution recommendations under application methods below. Transfer through a closed system appropriate amount of **FORMALDEHYDE SOLUTION 37** to the mixing tank containing appropriate amount of water. This product should be diluted with sufficient water to thoroughly wet all surfaces during application.

Sprinkler Application Method: Install sprinkler system in poultry or swine confinement building. Use plastic rain-bird impact sprinklers on six inch stands, spaced 20-30 feet apart using flexible 1/2 inch PVC irrigation hose. Some buildings may require two systems, one at each end covering one-half of building. Connect end of the sprinkler system to the truck or trailer mounted mix and pumping system or adapted agricultural spray rig. Close and secure door(s). Fumigate with **FORMALDEHYDE SOLUTION 37** by mixing 1 part **FORMALDEHYDE SOLUTION 37** with 10 parts water (a 1:11 dilution). All application activities must be carried out from outside confinement building. Application sprinklers should be rinsed following application solution with clean water, disconnected from pumping system, and left in confinement house until reentry is acceptable. Treated buildings should be left closed, locked and secured for a minimum of 24 hours, then, ventilated for sufficient time so that airborne levels of formaldehyde are less than 0.75 ppm as determined by an OSHA approved method used in accordance with manufacturer's instructions.

Spray Sled Application Method: Apply using a portable spray sled (such as U.S. Patent #5,489,066 method, Advance Pest Control, Lemoore, CA). Spray sled shall be of a design that allows it to spray formaldehyde solution in a rearward direction providing uniform coverage of sides, ceiling and floor as hose is recoiled and spray sled is pulled through poultry or swine confinement building. **Dilution:** Dilute **FORMALDEHYDE SOLUTION 37** with sufficient water to provide uniform coverage (recommended dilution rate - 1 part formaldehyde to 4 parts water).

Position vehicle carrying application pump delivery system approximately 20 feet from access to poultry or swine confinement building. Position spray sled equipment and feeder hose in poultry or swine confinement building at furthest distance from vehicle mounted pump delivery system. Spray formaldehyde solution in a rearward direction towards sides, ceiling and floor as hose is recoiled and spray sled is pulled through poultry or swine house. Keep entrance door closed to width of sled or approximately 30 inches. Follow application solution with sufficient clean water to flush sled system.

Pull sled out of poultry or swine below.

Treatment and Aeration of: secured against unauthorized

Note: For effectiveness, higher. Following treatment personal protective equipment (exchanges) of air exhausted, hours. If no mechanical vent

Reentry After Aeration: Do not be determined to be below 0.75 determined by direct reading

FOR USE IN DISINFECTING: the disinfection of mushroom

FORMALDEHYDE SOLUTION 37: label. No workers are permitted the mushroom house.

Remove all mushrooms, soil and sanitize with suitable solution.

Post warning signs on confinement immediate vicinity of all entrances building is safe for reentering Spanish, the following statement depict a skull and crossbones "FORMALDEHYDE", date performing the fumigation.

Trained personnel must be present necessary into treated confinement

PROCEDURE: WEAR FULL: FORMALDEHYDE.

APPLICATION:

- 1. Tools and Equipment: V of **FORMALDEHYDE**, with water to remove all
- 2. Non producing areas - co

- A. Empty mushroom house
- B. Wet out growing beds
- C. Close up house, seal
- D. Inject steam into house
- E. Inject FORMALDEHYDE (5 gallons in ft by 15 ft high).
- F. Continue steaming
- G. Turn on exhaust fan reentry, check house

Treatment and Aeration of Tr: authorized entry for a minimum building volumes (air exchanges air exchanges and 12 hours. If n

Reentry After Aeration: Do not been determined to be below 0.7 determined by direct reading dev

FOR USE IN CITRUS PACKING: For use in citrus packing house: sour rot, dosage should be 16 ft treated. Application to be made foggers. Units are to be controlled, may be used per room. Frequent permitted in treated building during treated. Allow formaldehyde r

Application Method: Room humidity in empty boxes, walls with tape to eliminate any significant house. Do not wet down with hose an elevated position, several feet hooked up to spray manifold and intake. All persons should leave turned on from a position outside should remain closed for a minimum thorough venting for a minimum to less than 0.75 ppm. Empty articles which may come in contact effective cleaning compound fol

Spray Manifold Application M: with sufficient water to provide treated, up to a dilution rate of 1

Pull sled out of poultry or swine house. Close and secure entrance door. Follow treatment period and aeration procedure below.

Treatment and Aeration of Treated Poultry Confinement Buildings: Treated buildings must be left closed, locked and secured against unauthorized entry for a minimum of 24 hours

Note: For effectiveness, relative humidity should be at least 70% and temperature at least 70°F (21 °C) or higher. Following treatment, rooms are opened to outside fresh air for thorough venting while using appropriate personal protective equipment. Removal of gas phase formaldehyde is a function of the number of building volumes (air exchanges) of air exhausted. If mechanical ventilation equipment is used, ventilate for a minimum of 20 air exchanges and 12 hours. If no mechanical ventilation equipment is used ventilate for a minimum of 24 hours.

Reentry After Aeration: Do not allow access into aerator treated areas by any person unless formaldehyde vapor level has been determined to be below 0.75 ppm. Warning signs may be removed only after vapor level drops below 0.75 ppm as determined by direct reading device, approved by OSHA and used in accordance with manufacturer's instructions

FOR USE IN DISINFECTION OF MUSHROOM HOUSES, TOOLS AND EQUIPMENT: This product may be used in the disinfection of mushroom houses, tools and equipment.

FORMALDEHYDE SOLUTION 37 can only be applied to unoccupied mushroom houses by the method following on this label. No workers are permitted in treated building during treatment. All application methods must be carried out from outside the mushroom house.

Remove all mushrooms, soil and debris from premises to assure adequate coverage. Remove all portable equipment. Clean and sanitize with suitable solutions as needed. Rinse all surfaces with water.

Post warning signs on confinement buildings prior to start of fumigation. Post signs in plainly visible locations on or in immediate vicinity of all entrances. Do not remove signs until fumigation, ventilation and final testing has been completed, and building is safe for reentering. Warning signs shall be printed in red on white background and shall contain, in English and Spanish, the following statement in letters not less than two inches in height: "DANGER - FUMIGATION". They shall also depict a skull and crossbones not less than one inch in height and shall state in letters not less than one-half inch in height "FORMALDEHYDE", date and time fumigant was introduced, and name, address and telephone number of the applicator performing the fumigation.

Trained personnel must be present during the introduction of formaldehyde and, after 24 - hour treatment period, if entry is necessary into treated confinement building for purposes of facilitating aeration.

PROCEDURE - WEAR FULL PROTECTIVE CLOTHING AND FULL FACE RESPIRATOR WHEN USING FORMALDEHYDE.

APPLICATION:

- 1 Tools and Equipment: Wash thoroughly with water to remove debris; then, dip with a solution made by mixing 1 gallon of FORMALDEHYDE SOLUTION 37 with tap water to make 100 gallons (a 0.37% solution of formaldehyde). Rinse with water to remove all traces of formaldehyde.
- 2 Non producing areas - corridors, packing sheds, empty growing sheds, etc.
 - A. Empty mushroom house of all growing media. Sweep out thoroughly.
 - B. Wet out growing boards.
 - C. Close up house, sealing as appropriate, to avoid formaldehyde fume seepage.
 - D. Inject steam into house until interior temperature reads 140 to 150°F [about 12 hours of steam injection required].
 - E. Inject FORMALDEHYDE SOLUTION 37 into steam [4 gallons in small houses of up to 37 ft by 48 ft by 15 ft high]; [5 gallons in regular dimension houses of 37 ft by 60 ft by 15 ft high]; [8 gallons in large houses 37 ft by 80 ft by 15 ft high].
 - F. Continue steaming for 12 hours.
 - G. Turn on exhaust fans for 4 hours and, then, open doors for 24 hours before permitting reentry into house. Prior to reentry, check house for formaldehyde fumes at outside of exhaust fans and at entrances.

Treatment and Aeration of Treated Mushroom Houses: Treated buildings must be left closed, locked and secured against unauthorized entry for a minimum forced ventilation period of 4 hours. Removal of gas phase is a function of the number of building volumes (air exchanges) of air exhausted. If mechanical ventilation equipment is used, ventilate for a minimum of 20 air exchanges and 12 hours. If no mechanical ventilation equipment is used, ventilate for a minimum of 24 hours.

Reentry After Aeration: Do not allow access into aerator treated areas by any person unless formaldehyde vapor level has been determined to be below 0.75 ppm. Warning signs may be removed only after vapor level drops below 0.75 ppm as determined by direct reading device, approved by OSHA and used in accordance with manufacturer's instructions.

FOR USE IN CITRUS PACKING HOUSES:

For use in citrus packing houses including storage, degreening and pre-cooling rooms to inhibit blue mold, green mold, sour rot, dosage should be 16 fluid ozs. of FORMALDEHYDE SOLUTION 37 per thousand cubic feet of space to be treated. Application to be made as a fogging spray using a stationary, mounted spray manifold and suitable air operated foggers. Units are to be controlled from outside area being fumigated. Where necessary, more than one manifold or fogger may be used per room. Frequency of application is to be limited twice per year for each packing house. No workers are permitted in treated building during treatment. Formaldehyde is phytotoxic to citrus. Remove all fruit from space to be treated. Allow formaldehyde residue to dissipate from storage boxes before filling with fruit.

Application Method: Room should be tightly closed and humidity introduced for at least 24 hours or longer to bring up humidity in empty boxes, walls and floors of room. Doors and windows that do not fit tightly should be sealed securely with tape to eliminate any significant escape of fumigant. Tape all suspected sources of leaks from outside the packing house. Do not wet down with hose. Air scrubbers should be drained and water pumps turned off. Place spray manifold in an elevated position, several feet off floor and close to a return for recirculating fan. A compressed air connection should be hooked up to spray manifold and recirculating fans turned on. Air should be on 100% recirculation with no outside air intake. All persons should leave room(s) and all doors, openings shut tightly. Compressed air to spray manifold should be turned on from a position outside area (room) to be treated. Turn fans off two (2) hours after fogging is completed. Room should remain closed for a minimum of twenty-four (24) hours. Room may then be opened to outside fresh air for thorough venting for a minimum of twenty-four (24) hours or longer until testing has shown formaldehyde has dissipated to less than 0.75 ppm. Empty field bins and degreening boxes can remain in rooms to be treated. Tools, equipment, and articles which may come in contact with citrus must be removed prior to treatment or thoroughly washed with an effective cleaning compound followed by a potable water rinse before reuse.

Spray Manifold Application Method: Dilution: FORMALDEHYDE SOLUTION 37 must be used undiluted or diluted with sufficient water to provide uniform coverage, dependent on the size of air recirculating capabilities of the area being treated, up to a dilution rate of 1 part FORMALDEHYDE SOLUTION 37 to 10 parts water

Fumigation is accomplished by dispersing formaldehyde gas from the top of carboy-type containers at an air pressure of 150 fluid capacity air or 1 1/4 inch brass fittings) are used and Dry-Cam Disconnect tightly for use. All contain name of the active ingr

All mixing and loading procedures should be done in a way that will result in the product being as uniform as possible (desirable). Tightly close container above, onto the container closed system liquid measure priming HP Pump (Pacer) quantity through the dry-break disconnect attached to site while avoiding loss o

Place container with spray nozzle for the recirculating fan. A connection should be hooked up to recirculation with no outside air tapping doors that have view of the area (room) to be treated. Spray manifold must be used. After fumigation, turn recirculation of (twenty-four (24) hours

Note: Fogging mechanism should be replaced with diluted FOR air pressure is required to be at least 80 to 100

Posting: Post warning signs in immediate vicinity of all entrances, and building should contain, in English and Spanish, "DANGER - FUMIGATION". They should be not less than one-half inch in height and shall state in letters not less than one-half inch in height the name, address and telephone number of the applicator.

Treatment and Aeration: Treated buildings must be left closed, locked and secured against unauthorized entry for a minimum of 24 hours. Removal of gas phase is a function of the number of building volumes (air exchanges) of air exhausted. If mechanical ventilation equipment is used, ventilate for a minimum of 20 air exchanges and 12 hours. If no mechanical ventilation equipment is used, ventilate for a minimum of 24 hours.

Reentry After Aeration: Do not allow access into aerator treated areas by any person unless formaldehyde vapor level has been determined to be below 0.75 ppm. Warning signs may be removed only after vapor level drops below 0.75 ppm as determined by direct reading device, approved by OSHA and used in accordance with manufacturer's instructions.

Note: For effectiveness, relative humidity should be at least 70% and temperature at least 70°F (21 °C) or higher.

Establish a worker buffer zone during treatment and aeration. Fumigation is accomplished by dispersing formaldehyde gas from the top of carboy-type containers at an air pressure of 1,000,000 cu. ft. Buffer zone ventilation, maintain buffer zone with passive means, maintain buffer zone with applicators or other equipment. The worker zone is acceptable from entering these zones

with its labeling.

ed on confinement buildings as determined during introduction of the

cubic feet of space to be treated. Place on floor, a large FORMALDEHYDE SOLUTION 37 container. Room may be reentered after aeration in accordance with

of 1 fl. oz. of FORMALDEHYDE SOLUTION 37. Use a minimum of 100 parts water. Worker's information should be provided and allowed to naturally dissipate as a catalyst to disinfect incubators containing hatcheries should also have area before fumigation may

Fumigation is most effective if done in hatchery or when set in incubator (5) days incubation because

of 1 fl. oz. of FORMALDEHYDE SOLUTION 37. Last at least 12 hours before chicks are introduced and warning signs may be removed when formaldehyde is below 0.75 ppm as determined by an

INGS: FORMALDEHYDE SOLUTION 37 may be used by either spray sled or manual application. All application

premises to assure adequate coverage. Clean all appropriate surfaces with a suitable and approved

ns in plainly visible locations and final testing has been completed. Warning signs shall contain, in English and Spanish, "DANGER-FUMIGATION". They shall state in letters not less than one-half inch in height the name, address and telephone

ON 37 and, after 24-hour treatment, facilitate aeration. Establish aeration by opening doors with cones and yellow cautionary

of building to be treated. Use 16 fluid ozs. of FORMALDEHYDE SOLUTION 37 per thousand cubic feet of building volume. Transfer through a closed system of appropriate amount of water. Clean during application

t building. Use plastic rain-bird irrigation hose. Some buildings have the sprinkler system to the outside and secure door(s). Fumigate with FORMALDEHYDE SOLUTION 37 with 10 parts water (a 1:10 dilution). Application sprinklers should be used. Room should be locked and secured for a minimum of 24 hours or longer until testing has shown formaldehyde has dissipated to less than 0.75 ppm as determined by direct

it #5,489,066 method, Advance FORMALDEHYDE SOLUTION 37 is applied through a spray sled is pulled through a container with sufficient water to

ccess to poultry or swine confinement building at furthest end of building towards sides. Use. Keep entrance door closed. Clean water to flush sled system.

ment period and aeration procedure

gs must be left closed, locked and

ure at least 70°F (21 °C) or
ting while using appropriate
e number of building volumes (air
minimum of 20 air exchanges and 12
ours.

less formaldehyde vapor level has
apor level drops below 0.75 ppm as
1 manufacturer's instructions.

EMENT: This product may be used in

es by the method following on this
ods must be carried out from outside

ove all portable equipment. Clean and

ainly visible locations on or in
l final testing has been completed, and
l and shall contain, in English and
- FUMIGATION". They shall also
less than one-half inch in height
telephone number of the applicator

hour treatment period, if entry is

ATOR WHEN USING

h a solution made by mixing 1 gallon
7% solution of formaldehyde] Rinse

2 hours of steam injection required]
ouses of up to 37 ft by 48 ft by 15 ft
[8 gallons in large houses 37 ft by 80

mitting reentry into house Prior to
it entrances.

closed, locked and secured against
se is a function of the number of
s used, ventilate for a minimum of 20
a minimum of 24 hours.

less formaldehyde vapor level has
level drops below 0.75 ppm as
nufacturer's instructions

to inhibit blue mold, green mold,
housand cubic feet of space to be
y manifold and suitable air operated
y, more than one manifold or fogger
t packing house. No workers are
**Remove all fruit from space to be
y with fruit.**

least 24 hours or longer to bring up
tightly should be sealed securely
of leaks from outside the packing
turned off. Place spray manifold in
compressed air connection should be
ecirculation with no outside air
ssed air to spray manifold should be
rs after fogging is completed. Room
ened to outside fresh air for
shown formaldehyde has d ripated
o be treated. Tools, equipment, and
thoroughly washed with an

must be used undiluted or diluted
ating capabilities of the area being
water.

Fumigation is accomplished by using one or more spray manifold units, each having two to four nozzles mounted onto the top of carboy-type containers. (Five-gallon capacity recommended.) These nozzles must be designed to give adequate dispersal at an air pressure of 50 to 100 p.s.i. The nozzles are further specified as 1/4 J set-up #5 (180 air capacity, 100-150 fluid capacity) air orifice 100-150 (Spray Systems, Inc. Wheaton, IL) or equivalent. Spray manifolds (plumbed with 1 4 inch brass fittings) are fitted through a carboy-type container cap with drilled holes for spray manifold with siphon tube and Dry-Cam Disconnect DC-100A dry-break disconnect attachment (S & R Specialties, Cocoran, CA) or equivalent, sealed tightly for use. All containers of formaldehyde, including carboy-type containers must be plainly labeled with the name of the active ingredient, **FORMALDEHYDE**

All mixing and loading procedures must be performed using closed systems. Fill carboy-type container with water to level that will result in the proper dilution of **FORMALDEHYDE SOLUTION 37** (for applications where dilution is desirable). Tightly close the modified top of the carboy-type container, fitted with the spray manifold unit as described above, onto the container. Transfer the appropriate amount of **FORMALDEHYDE SOLUTION 37** into a Chemsure III closed system liquid measurement device (Cherlor Mfg. Co., Inc., Salinas, CA), or equivalent, using a Pacer-Pump self-priming HP Pump (Pacer Pumps, Leola, PA), or equivalent hand pump. Use the same pump to transfer the measured quantity through the dry-break disconnect attachment into closed carboy-type container fitted with the spray manifold. The dry-break disconnect attachment at the carboy-type container should allow the filled bottle to be moved to the fumigation site while avoiding loss of fluids.

Place container with spray manifold in an elevated position, several feet off the floor and, where possible close to a return for the recirculating fan. Where necessary more than one manifold or fogger may be used per room. A compressed air connection should be hooked up to the spray manifold and the recirculating fans turned on. Air should be on 100% recirculation with no outside air intake. All persons must leave room(s) and all doors, openings shut tightly, (securely taping doors that have visible gaps). Compressed air to the spray manifold must be turned on from a position outside the area (room) to be treated. Adequate air pressure is necessary to obtain proper dispersion of the formaldehyde. Each spray manifold must use about 40 cubic feet of free air per minute at 80 to 100 p.s.i.. Without reentering rooms being fumigated, turn recirculating fans off two (2) hours after fogging is completed. Room must remain closed for a minimum of twenty-four (24) hours.

Note: Fogging mechanism must be checked with water in carboy (reservoir) prior to use. After testing, dump water and replace with diluted **FORMALDEHYDE SOLUTION 37**. A closed, mixing and dispensing system is required. Adequate air pressure is required to obtain proper dispersion of formaldehyde. Each fogger manifold uses about 40 cubic feet of free air per minute at 80 to 100 p.s.i.

Posting: Post warning signs on citrus packing houses prior to start of fumigation. Post signs in plainly visible locations on or in immediate vicinity of all entrances. Do not remove signs until fumigation, ventilation and final testing has been completed, and building is safe for reentering. Warning signs shall be printed in read on white background and shall contain, in English and Spanish, the following statement in letters not less than two inches in height: "**DANGER-FUMIGATION**". They shall also depict a skull and crossbones not less than one inch in height and shall state in letters not less than one-half inch height "**FORMALDEHYDE**", date and time fumigant was introduced, and name, address and telephone number of the applicator performing the fumigation

Treatment and Aeration of Citrus Facilities: Treated buildings must be left closed, locked and secured against unauthorized entry for a minimum of 24 hours. Following treatment, rooms are opened to outside fresh air for thorough venting while using appropriate personal protective equipment. Removal of gas phase formaldehyde is a function of the number of building volumes (air exchanges) of air exhausted. If mechanical ventilation equipment is used, ventilate for a minimum of 20 air exchanges and 12 hours. If no mechanical ventilation equipment is used, ventilate for a minimum of 24 hours.

Reentry After Aeration: Do not allow access into aerator treated areas by any person unless formaldehyde vapor level has been determined to be below 0.75 ppm. Warning signs may be removed only after vapor level drops below 0.75 ppm as determined by direct reading device, approved by OSHA and used in accordance with manufacturer's instructions.

Note: For effectiveness, relative humidity should be at least 70% and temperature at least 70°F (21 °C) or higher.

Buffer Zones:

Establish a worker buffer zone of 25 feet and a residential buffer zone extending from and surrounding the treated building during treatment and aeration. Determine the residential buffer zone based on the volume (cubic feet) of the structure being fumigated using a range of less than 100,000 cu. ft. requiring a buffer zone of 150 ft. to a zone of 1100 ft for buildings of 1,000,000 cu. ft. Buffer zone tables are available from the distributor. If aeration is conducted with mechanical exhaust ventilation, maintain buffer zones for 12 hour and until 20 air exchanges of air have been exhausted. If enclosure is aerated by passive means, maintain buffer zones for 24 hours. Access to the area within the worker buffer zone is acceptable for applicators or other employees with respiratory protection. Access to the larger area within the residential buffer zone outside the worker zone is acceptable for other employees and others that are not residing within the residential buffer zone. Keep all others from entering these zones while in place.

