



## OFFICE OF CHEMICAL SAFETY AND POLLUTION PREVENTION

WASHINGTON, D.C. 20460

April 25, 2024

Haley Wade  
Lead Regulatory Manager  
Control Solutions Inc.  
5903 Genoa-Red Bluff  
Pasadena, TX 77507-1041

Subject: Label Amendment – To add EAB language and a reduced water rate in the instance of drought conditions (or areas with water restrictions).  
Product Name: IMI 2 LB Insecticide  
EPA Registration Number: 53883-229  
Application Date: January 30, 2019; September 30, 2022  
Case Number: 605957; 479687

Dear Haley Wade:

The amended label referred to above, submitted in connection with registration under the Federal Insecticide, Fungicide, and Rodenticide Act (FIFRA), as amended, is acceptable. This approval does not affect any conditions that were previously imposed on this registration. You continue to be subject to existing conditions on your registration and any deadlines connected with them.

A stamped copy of your labeling is enclosed for your records. This labeling supersedes all previously accepted labeling. You must submit one copy of the final printed labeling before you release the product for shipment with the new labeling. In accordance with 40 CFR 152.130(c), you may distribute or sell this product under the previously approved labeling for 18 months from the date of this letter. After 18 months, you may only distribute or sell this product if it bears this new revised labeling or subsequently approved labeling. "To distribute or sell" is defined under FIFRA section 2(gg) and its implementing regulation at 40 CFR 152.3.

Should you wish to add/retain a reference to the company's website on your label, then please be aware that the website becomes labeling under FIFRA and is subject to review by the Agency. If the website is false or misleading, the product would be misbranded and unlawful to sell or distribute under FIFRA section 12(a)(1)(E). 40 CFR 156.10(a)(5) lists examples of statements EPA may consider false or misleading. In addition, regardless of whether a website is referenced on your product's label, claims made on the website may not substantially differ from those claims approved through the registration process. Therefore, should the Agency find or if it is brought to our attention that a website contains false or misleading statements or claims substantially differing from the EPA approved registration, the website will be referred to the EPA's Office of Enforcement and Compliance.

Page 2 of 2

EPA Reg. No. 53883-229

Case No. 479687; D605957


Your release for shipment of the product constitutes acceptance of these conditions. If these conditions are not complied with, the registration will be subject to cancellation in accordance with FIFRA section 6.

If you have any questions, please contact Andrés Garzón at (202) 566-2690 or at [GarzonMoreno.Andres@epa.gov](mailto:GarzonMoreno.Andres@epa.gov).

Sincerely,

A handwritten signature in black ink, appearing to read "Venus Eagle", with a stylized flourish at the end.

Venus Eagle, Product Manager 01  
Invertebrate & Vertebrate Branch 3  
Registration Division (7505P)  
Office of Pesticide Programs



Imidacloprid	GROUP	4A	INSECTICIDE
--------------	-------	----	-------------

# IMI 2 Ib Insecticide

[alt. brand name: Dominion 2L Insecticide/Termiticide] [alt. brand name: Dominion 2L][alt. brand name: Dominion 2L Termiticide/Insecticide]

## FOLIAR AND SYSTEMIC INSECT CONTROL

*FOR USE ON TURFGRASS (INCLUDING, LANDSCAPE ORNAMENTALS, FRUIT AND NUT TREES AND INTERIOR PLANTSCAPES.*

*PREVENTS AND CONTROLS SUBTERRANEAN TERMITES, DRYWOOD TERMITES, DAMPWOOD TERMITES, [and] CARPENTER ANTS, AND OTHER WOOD-INFESTING INSECTS*

**For use by professional personnel licensed or registered by the state to apply termiticide, when used as a termiticide. States may have more restrictive requirements regarding qualifications of persons using this product. Consult the structural pest control regulatory agency of your state prior to use of this product.**

**ACTIVE INGREDIENT:**

Imidacloprid: 1-1(6-Chloro-3-pyridinyl)methyl]-N-nitro-2-imidazolidinimine ..... 21.4%

**OTHER INGREDIENTS:** ..... 78.6%

---

Total: 100.0%

Contains 2 pounds of imidacloprid per gallon.

Shake well before using.



**Manufactured for:**  
Control Solutions, Inc.  
5903 Genoa Red Bluff[Rd][Road]  
Pasadena, TX 77507

EPA Reg. No: 53883-229  
EPA Est. No: \_\_\_\_\_  
Net Contents: \_\_\_\_\_  
{Lot number will be printed on the container}

Consumer & Professional Solutions

**Keep out of reach of children**

## CAUTION

PRECAUCION AL USUARIO: Si usted no puede leer o entender ingles, no use este producto hasta que la etiqueta le haya sido explicada ampliamente.

(TO THE USER: If you cannot read or understand English, do not use this product until the label has been fully explained to you.)

FIRST AID	
<b>If Swallowed</b>	<ul style="list-style-type: none"> <li>• Call a poison control center or doctor immediately for treatment advice.</li> <li>• Have person sip a glass of water <i>if</i> able to swallow.</li> <li>• Do not induce vomiting unless told to do so by a poison control center or doctor.</li> <li>• Do not give anything by mouth to an unconscious person.</li> </ul>
<b>If Inhaled</b>	<ul style="list-style-type: none"> <li>• Move person to fresh air.</li> <li>• If person is not breathing, call 911 or an ambulance, then give artificial respiration, preferably mouth-to-mouth, if possible.</li> <li>• Call a poison control center or doctor for further treatment advice.</li> </ul>

<b>If on Skin or Clothing</b>	<ul style="list-style-type: none"> <li>• Take off contaminated clothing</li> <li>• Rinse skin immediately with plenty of soap and water for 15 to 20 minutes.</li> <li>• Call a poison control center or doctor for treatment advice.</li> </ul>
<b>If in Eyes</b>	<ul style="list-style-type: none"> <li>• Hold eyelids open and rinse slowly and gently with water for 15 to 20 minutes.</li> <li>• Remove contact lenses, if present, after the first 5 minutes, then continue rinsing eye.</li> <li>• Call a poison control center or doctor for treatment advice.</li> </ul>
<b>HOT LINE NUMBER</b>	
Have the product container or label with you when calling a poison central center or doctor, or going for treatment. You may also contact SafetyCall® International (866) 897-8050 for emergency medical treatment information.	
<b>NOTE TO PHYSICIAN</b>	
No specific antidote is available. Treat patient symptomatically.	

**PRECAUTIONARY STATEMENTS**  
**HAZARDS TO HUMANS AND DOMESTIC ANIMALS**

**CAUTION:** Harmful if swallowed, inhaled, or absorbed through skin. Avoid contact with skin, eyes, or clothing. Avoid breathing spray mist. Wash thoroughly with soap and water after handling. Remove contaminated clothing and wash before reuse. Keep children or pets away from treated area until dry.

**Personal Protective Equipment (PPE)**

Personal Protective Equipment (PPE):

Applicators and other handlers (mixers and loaders) must wear:

- Long-sleeved shirt and long pants
- Chemical-resistant gloves made of any waterproof material such as barrier laminate, butyl rubber ≥ 14 mils, nitrile rubber ≥ 14 mils, neoprene rubber ≥ 14 mils, natural rubber ≥ 14 mils, polyvinylchloride (PVC) ≥ 14 mils or viton ≥ 14 mils.
- Shoes plus socks

In addition: all pesticide handlers must wear protective eyewear when working in a non-ventilated space or when applying termiticide by rodding or sub-slab injection.

Follow manufacturer's instructions for cleaning/maintaining PPE. If no such instructions for washables, use detergent and hot water. Keep and wash PPE separately from other laundry.

**Engineering controls statements:** When handlers use closed systems, enclosed cabs, or aircraft in a manner that meets the requirements listed in the Worker Protection Standard (WPS) for agricultural pesticides [40 CFR 170.240(4)(4-6)], the handler PPE requirements may be reduced or modified as specified in the WPS.

**USER SAFETY RECOMMENDATIONS**

**User should:**

- Wash thoroughly with soap and water after handling and before eating, drinking, chewing gum, or using tobacco.
- Remove and wash contaminated clothing before reuse.

**ENVIRONMENTAL HAZARDS**

This product is highly toxic to aquatic invertebrates. Do not apply directly to water, to areas where surface water is present or to intertidal areas below the mean high-water mark. Do not contaminate water when disposing of equipment washwaters.

This product is highly toxic to bees exposed to direct treatment or residues on blooming plants or weeds. Do not apply this product or allow it to drift to blooming plants or weeds if bees are foraging in the treatment area.

This chemical demonstrates the properties and characteristics associated with chemicals detected in groundwater. The use of this chemical in areas where soils are permeable, particularly where the water table is shallow, may result in groundwater contamination.

Apply this product only as specified on this label. Extreme care must be taken to avoid runoff. Apply only to soil or other fill substrate that will accept the solution at the specified rate. Do not treat soil that is water-saturated or frozen or in any conditions where run-off or movement from the treatment area (site) is likely to occur.

## PROTECTION OF POLLINATORS



**APPLICATION RESTRICTIONS** EXIST FOR THIS PRODUCT BECAUSE OF RISK TO BEES AND OTHER INSECT POLLINATORS. FOLLOW APPLICATION RESTRICTIONS FOUND IN THE DIRECTIONS FOR USE TO PROTECT POLLINATORS.



Look for the bee hazard icon in the Directions for Use for each application site for specific use restrictions and instructions to protect bees and other insect pollinators.

**This product can kill bees and other insect pollinators.**

Bees and other insect pollinators will forage on plants when they flower, shed pollen, or produce nectar.

Bees and other insect pollinators can be exposed to this pesticide from:

- Direct contact during foliar applications, or contact with residues on plant surfaces after foliar applications
- Ingestion of residues in nectar and pollen when the pesticide is applied as a seed treatment, soil, tree injection, as well as foliar applications.

When Using This Product Take Steps To:

- Minimize exposure of this product to bees and other insect pollinators when they are foraging on pollinator attractive plants around the application site.
- Minimize drift of this product on to beehives or to off-site pollinator attractive habitat. Drift of this product onto beehives or off-site to pollinator attractive habitat can result in bee kills.

Information on protecting bees and other insect pollinators may be found at the Pesticide Environmental Stewardship website at: <http://pesticidestewardship.org/PollinatorProtection/Pages/default.aspx>.

Pesticide incidents (for example, bee kills) should immediately be reported to the state/tribal lead agency. For contact information for your state, go to: [www.aapco.org/officials.html](http://www.aapco.org/officials.html). Pesticide incidents should also be reported to the National Pesticide Information Center at: [www.npic.orst.edu](http://www.npic.orst.edu) or directly to EPA at: [beekill@epa.gov](mailto:beekill@epa.gov).

## DIRECTIONS FOR USE

It is a violation of Federal law to use this product in a manner inconsistent with its labeling.



Do not apply IMI 2 lb Insecticide while bees are foraging. Do not apply IMI 2 lb Insecticide to plants that are flowering. Only apply after all flower petals have fallen off.

Do not apply this product in a way that will contact workers or other persons, either directly or through drift. Only protected handlers may be in the area during application. For any requirements specific to your State or Tribe, consult the agency responsible for pesticide regulation.

## Resistance Management

For resistance management, IMI 2lb Insecticide contains a Group 4A insecticide. Any insect population may contain individuals naturally resistant to IMI 2lb Insecticide and other Group 4A insecticides. The resistant individuals may dominate the insect population if this group of insecticides are used repeatedly in the same fields. Appropriate resistance-management strategies should be followed.

To delay insecticide resistance, take the following steps:

- Use tank mixtures with insecticides from a different group that are equally effective on the target pest when such use is permitted. Do not rely on the same mixture repeatedly for the same pest population. Consider any known cross-resistance issues (for the targeted pests) between the individual components of a mixture. In addition, consider the following recommendations provided by the Insecticide Resistance Action Committee (IRAC):
  - Individual insecticides selected for use in mixtures should be highly effective and be applied at the rates at which they are individually registered for use against the target species.
  - Mixtures with components having the same IRAC mode of action classification are not recommended for insect resistance management.
  - When using mixtures consider any known cross-resistance issues between the individual components for the targeted pest(s)
  - Mixtures become less effective if resistance is already developing to one or both active ingredients, but they may still

- provide pest management benefits.
- The insect resistance management benefits of an insecticide mixture are greatest if the two components have similar periods of residual insecticidal activity. Mixtures of insecticides with unequal periods residual insecticide activity may offer an insect resistance management benefit only for the period where both insecticides are active.
- Monitor after application for unexpected target pest survival. If the level of survival suggests the presence of resistance, consult with your local university specialist or certified pest control advisor.
- For further information or to report suspected resistance contact Control Solutions, Inc at 800-242-5562 or at [www.controlsolutionsinc.com](http://www.controlsolutionsinc.com)

## APPLICATION AS A TERMITICIDE

IMI 2 LB INSECTICIDE may be used in and along outside perimeter of structures and building construction to prevent and control termite infestations.

## USE INSTRUCTIONS

For subterranean termite control, specific treatment instructions may differ due to regulations, treatment procedures, soil types, construction practices and other factors. The purpose of chemical soil treatment for termite control is to establish a continuous chemical treated zone (horizontal and/or vertical) between the wood and other cellulose material in the structure and the termite colonies in the soil. Follow all federal, state, and local regulations and treatment standards for protection of a structure from termites. The establishment of an aerial or above ground colony may require additional treatments to control the termites, as well as landscape modifications, and/or structural repairs to deny termites of a moisture source. Use a 0.05% to 0.1% dilution based on current practices. For a typical control situation, a 0.05% dilution is used. A 0.1% dilution may be used when a severe or persistent infestation exists.

When treating adjacent to an existing structure, the applicator must check the area to be treated, and immediately adjacent areas of the structure, for visible and accessible cracks and holes to prevent any leaks or significant exposures to persons occupying the structure. People present or residing in the structure during application must be advised to remove their pets and themselves from the structure if they see any signs of leakage. After application, the applicator is required to check for leaks. All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site. Do not allow people or pets to contact contaminated areas or to reoccupy contaminated areas of the structure until the cleanup is completed.

Structures that contain wells or cisterns within the foundation of the structure can only be treated using the treated backfill method described in the treatment around wells and cisterns section of this label. Consult state and local specifications for recommended distances of wells from treated area, or if such regulations do not exist, refer to Federal Housing Administration Specifications (H.U.D.) for guidance.

**MIXING:** Refer to **MIXING TABLE** for correct amount of IMI 2 LB INSECTICIDE to be used.

Follow this procedure for mixing the termiticide dilution:

1. Fill tank to 1/3 full.
2. If using large sprayer, start pump to begin bypass agitation and place end of treating tool in tank to allow circulation through hose.
3. Add appropriate amount of IMI 2 LB INSECTICIDE. Add remaining amount of water. Let pump run and allow recirculation through the hose for 2 to 3 minutes.

[Only one of the tables below will be used based upon the size of container offered for sale]

[For 55 fl oz size only]

MIXING TABLE FOR IMI 2 LB INSECTICIDE		
EMULSION CONCENTRATE	GALLONS WATER	AMOUNT OF IMI 2 LB
0.05%	100	27.5 fl oz
	50	13.8 fl. oz.
	25	6.9 fl oz
	1	0.3 fl oz
0.1%	100	55.0 fl. oz.
	50	27.5 fl oz
	25	13.8 fl oz
	1	0.6 fl oz

[For 240 mL size only]

MIXING TABLE FOR IMI 2 LB INSECTICIDE		
EMULSION CONCENTRATE	GALLONS WATER	AMOUNT OF IMI 2 LB
0.05%	10	80 mL
	5	40 mL
	2	16 mL
	1	8 mL
0.1%	10	160 mL
	5	80 mL
	2	32 mL
	1	16 mL

**IN-LINE INJECTION:** Use the table below to mix the appropriate amount of IMI 2 LB INSECTICIDE for the desired injection volume of finished emulsion.

MIXING TABLE - INJECTOR	
INJECTOR VOLUME	CONCENTRATION
0.3 fl oz/gal	0.05%
0.6 fl oz/gal	0.1%

CONVERSION KEY: 128 fl oz = 1 gal; 16 fl oz = 1 pint; 8 pints = 1 gal; 1 fl oz = 29.5 mL

### APPLICATION VOLUME

To provide maximum control and protection against termite infestation, apply the specified volume of the finished water emulsion and active ingredient as set forth in the directions for use section of this label. In cases of insufficient water supply, mandatory reductions in local water use or if soil will not accept the labeled application volume, the volume may be reduced provided there is a corresponding increase in concentration so that the amount of active ingredient applied to the soil remains the same.

**Note:** Large reductions of application volume reduce the ability to obtain a continuous barrier. Variance is

allowed when volume and concentration are consistent with label directed rates and a continuous barrier can still be achieved.

## PRE-CONSTRUCTION TREATMENT

Do not apply at a lower dosage and/or concentration than specified on this label for application prior to installation of the finished grade.

Prior to each application, applicators must notify the general contractor, construction superintendent, or similar responsible party, of the intended termiticide application and intended sites of application and instruct the responsible person to notify construction workers and other individuals to leave the area to be treated during application and until the termiticide is absorbed into the soil.

**CONCRETE SLAB-ON-GROUND OR BASEMENTS:** Apply an overall treatment to the entire surface of soil or other substrate to be covered by the slab including areas to be under carports, porches, basement floor and entrance platforms. Apply at the rate of 1 gallon of solution to accurately and uniformly cover 10 square feet. If fill under slab is gravel or other coarse aggregate, apply at the rate of 1.5 gallons or sufficient volume of solution, to accurately and uniformly cover 10 square feet. In addition, apply 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet to provide a uniform treated zone in soil at critical areas such as along the inside of foundation walls, and around plumbing, bath traps, utility services, and other features that will penetrate the slab.

After completion of grading, make an application by trenching or trenching and rodding around the slab or foundation perimeter. Rodding may be done from the bottom of a shallow trench. When rodding, rod holes must be spaced in a manner that will allow for a continuous chemical treated zone, not to exceed 12 inches, to be deposited along the treated area. Rod holes must not extend below the footing. Apply 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet, per foot of depth to provide a uniform treated zone. When trenching, the trench along the outside foundation must be about 6 inches in width and 6 inches in depth. Use a low pressure spray (not to exceed 25 PSI at the treatment tool when the valve is open) to treat soil which will be placed in the trench after rodding. Mix the spray solution with soil as it is being placed in the trench. When treating voids in hollow masonry units, use 2 gallons of solution per 10 linear feet of wall. Apply solution so it will reach the footing by injecting into the lower areas of the wall, just above the floor or footing.

When treating foundations deeper than 4 feet, apply the termiticide as the backfill is being replaced, or if the construction contractor fails to notify the applicator to permit this, treat the foundation to a minimum depth of 4 feet after the backfill has been installed. The applicator must trench and rod into the trench or trench along the foundation walls and around pillars and other foundation elements, at the rate prescribed from grade to a minimum depth of 4 feet. When the top of the footing is exposed, the applicator must treat the soil adjacent to the footing to a depth not to exceed the bottom of the footing. Do not treat structures below the footing.

Rodding in trench followed by flooding of trench and treatment of backfill may provide a better opportunity to achieve a continuous chemical treated zone than using soil rodding alone to establish a vertical termiticide treated zone.

**CRAWL SPACES:** Application must be made by trenching or trenching and rodding downward along the inside and outside of foundation walls, around piers, interior supports in contact with the soil, plumbing, and utility services. Apply 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet, per foot of depth to provide a uniform treated zone. Rodding may be done from the bottom of a shallow trench to top of the footing or a minimum of 4 feet. When rodding, rod holes must be spaced in a manner that will allow for a continuous chemical treated zone to be deposited along the treated area. Rod holes must not extend below the footing. When trenching, the trench must be about 6 inches wide and 6 inches deep. Use a low pressure spray to treat soil which will be placed in the trench, mixing the spray solution with soil as it is being placed in the trench.

**HOLLOW BLOCK FOUNDATIONS OR VOIDS:** Hollow block foundations or voids in masonry resting on the footing may be treated to provide a continuous chemical treated zone in the voids at the footing. Apply 2 gallons of solution per 10 linear feet to the lower part of the void so that it reaches the top of the footing or soil.

Treatment of voids in block or rubble foundation walls must be closely examined. Applicators must inspect areas of possible runoff as a precaution against application leakage in the treated areas. Some areas may not be treatable or may require mechanical alteration prior to treatment.

All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site (refer to **PRECAUTIONARY STATEMENTS**). Do not allow people or pets to contact or to reoccupy the contaminated areas of the structure until the cleanup is completed.

## POST-CONSTRUCTION TREATMENT

**CONCRETE SLAB-ON-GROUND:** To apply a treatment under the slab, including attached porches, carports, entrance platforms, garages and similar slab structures, it may be necessary to drill through the slab or exterior foundation. Drill holes must be spaced in a manner that will allow for application of a continuous chemical treated zone. Treat all existing cracks and cold, construction or expansion joints. Also, treat around bath traps, plumbing and utility services which penetrate the slab. Apply 4 gallons of solution (see



**APPLICATION VOLUME**) per 10 linear feet per foot of depth to provide a uniform treated zone. DO NOT MAKE TREATMENT UNTIL LOCATION OF HEAT OR AIR CONDITIONING DUCTS AND VENTS ARE KNOWN AND IDENTIFIED. USE EXTREME CAUTION TO AVOID CONTAMINATION OF DUCTS AND VENTS. Plug and fill all drilled holes in commonly occupied areas with a suitable sealant. Plugs must be of non-cellulose material or covered by an impervious, non-cellulose material.

Apply by trenching or trenching and rodding around the outside of the foundation wall. Apply 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet per foot of depth to provide a uniform treated zone. When trenching, the trench along the outside foundation must be about 6 inches wide and 6 inches deep. Use a low-pressure spray to treat soil as it is being placed in the trench.

Rodding can be done from the bottom of a shallow trench. When rodding, rod holes must be spaced in a manner that will allow for a continuous chemical treated zone, not to exceed 12 inches, to be deposited along the treated area. Rod hole depth must not extend below the footing.

**BATH TRAPS or OTHER EXPOSED SOIL:** Exposed soil after foundation removal/repair, bath traps, or soil covered with tar or a similar type of sealant beneath and around plumbing and/or drain pipe entry areas should be treated with 3 gallons of solution per square foot. An access door or inspection vent should be cut and installed, if not already present. After inspection and removal of any wood or cellulose debris, the soil can be treated by rodding or drenching the soil.

**CRAWL SPACES:** When there is insufficient clearance between floor joists and ground surfaces to allow applicator access, excavate, if possible, and treat according to crawl spaces (refer to **PRE-CONSTRUCTION TREATMENT**). If unable to excavate, crawl space soil and wood treatment may be used to prevent surface access by termites. Apply 1 gallon of solution (see **APPLICATION VOLUME**) per 10 square feet to provide a uniform chemical treated zone. Use a very coarse spray at a pressure not exceeding 25 PSI at the treatment tool when the valve is open.

Where a crawl space cannot be reached with the application wand, use extension wands or other suitable equipment to apply a coarse spray on the soil, wood and structural members contacting the soil at the above rates. Do not apply to inaccessible crawl space areas using pressures greater than 25 PSI at the treatment tool when the valve is open.

Treatment may also be made by drilling through the foundation wall or through the floor above and treating the soil perimeter at a rate of 1 gallon of solution per 10 square feet. Drill spacing must be at intervals not to exceed 16 inches. Many states have smaller intervals so check state regulations which may apply.

To prevent subterranean termites from constructing mudtubes between soil and crawl space wood members above, an overall soil treatment of this product may be applied. Remove all cellulose debris before application. Apply 1 gallon of solution (see **APPLICATION VOLUME**) per 10 square feet to provide a uniform chemical treated zone.

**SHALLOW FOUNDATIONS:** For shallow foundations, one foot or less in depth, dig a narrow trench approximately 6 inches wide and deep along the outside and inside of the foundation walls, being careful not to dig below the bottom of the footings. For foundations with exposed footings, dig a trench alongside the footing taking care not to undermine the footing. Apply 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet to the top of footer to provide a uniform treated zone. The dilution must be applied to the trench and mixed with the soil as it is placed in the trench.

**BASEMENTS - OUTSIDE PERIMETER:** Along the outside of the exterior walls, an application must be made by trenching or rodding within the trench. Rodding depth should be to the top of the footer, or to a minimum of 4 feet or according to state or local regulations. When rodding through a trench, dig a narrow trench about 6 inches wide and 6 inches deep. Apply 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet, per foot of depth to provide a uniform treated zone by rodding through the trench. Use a low-pressure spray to treat soil which will be placed into the trench after rodding. Mix spray solution with the soil as it is being placed in the trench.

**BASEMENTS - INSIDE PERIMETER:** If necessary, treat by drilling along the perimeter of the interior walls. Applications also may be necessary around Sewer pipes, floor drains, conduits, expansion joints or any cracks or holes in the basement floor. Apply 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet to provide a uniform treated zone.

Drill holes must be spaced in a manner that will allow for application of a continuous chemical treated zone. Plug and fill all drill holes in commonly occupied areas of the building with a suitable sealant. Plugs must be of non-cellulose material or covered by an impervious, non-cellulose material.

**HOLLOW BLOCK FOUNDATION OR VOIDS:** Hollow block foundations or voids in masonry resting on the footing may be treated to provide a continuous chemical treated zone in the voids at the footing. Apply 2 gallons of solution per 10 linear feet to the lower part of the void so that it reaches the top of the footing or soil. Drill spacing must be at intervals not to exceed 16 inches. Many states have smaller intervals so check state regulations which may apply.

Treatment of voids in block or rubble foundation walls must be closely examined. Applicators must inspect areas of possible runoff as a precaution against application leakage in the treated areas. Some areas may not be treatable or may require mechanical alteration prior to treatment.

All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site (refer to **PRECAUTIONARY STATEMENTS**). Do not allow people or pets to contact or to reoccupy the contaminated areas of the structure until the cleanup is completed.

**PLENUMS:** For plenum-type structures which use a sealed underfloor space to circulate heated and/or cooled air throughout the structure, apply the dilution at the rate of 4 gallons of solution (see **APPLICATION VOLUME**) per 10 linear feet, per foot of depth of soil to provide a uniform treated zone adjacent to both sides of foundation walls, supporting piers, plumbing and conduits. Treat soil by trenching to a depth of 6 inches or trenching and rodding (where conditions permit) or to the top of the footing. When conditions will not permit trenching or rodding, a surface application adjacent to interior foundation walls may be made, but the treated strip shall not exceed a width of 18 inches, horizontally, from the foundation walls, piers or pipes. The surface application will be made at a rate of 1.5 gallons of solution per 10 square feet as a very coarse spray under low pressure (not to exceed 25 PSI when measured at the treating tool when valve is on).

When treating plenums, turn off the air circulation system of the structure until application has been completed and all termiticide has been absorbed by the soil.

**TREATMENT AROUND WELLS OR CISTERNS:** Do not contaminate wells or cisterns.

**Structures With Wells/Cisterns Inside Foundations:** Structures that contain wells or cisterns within the foundation of a structure can only be treated using the following techniques:

1. Do not apply within 5 feet of any well or cistern by rodding and/or trenching or by the backfill method. Treat soil between 5 and 10 feet from the well or cistern by the backfill method only. Treatment of soil adjacent to water pipes within 3 feet of grade should only be done by the backfill method.
  - a) Trench and remove soil to be treated onto heavy plastic sheeting or similar material or into a wheelbarrow.
  - b) Treat the soil at the rate of 4 gallons of solution per 10 linear feet per foot of depth of the trench, or 1 gallon per 1.0 cubic feet of soil. Mix thoroughly into the soil taking care to contain the liquid and prevent runoff or spillage.
  - c) After the treated soil has absorbed the solution, replace the soil into the trench.
2. Treat infested and/or damaged wood in place using an injection technique such as described in the **CONTROL OF WOOD INFESTING PESTS** section of this label.

**Structures With Adjacent Wells/Cisterns and/or Other Water Bodies:** Applicators must inspect all structures with nearby water sources such as wells, cisterns, surface ponds, streams, and other bodies of water and evaluate, at a minimum, the treatment recommendations listed below prior to making an application.

1. Prior to treatment, if feasible, expose the water pipes coming from the well to the structure, if the pipes enter the structure within 3 feet of grade.
2. Prior to treatment applicators are advised to take precautions to limit the risk of applying the termiticide into subsurface drains that could empty into any bodies of water. These precautions include evaluating whether application of the termiticide to the top of the footer may result in contamination of the subsurface drain. Factors such as depth to the drain system and soil type and degree of compaction must be taken into account in determining the depth of treatment.
3. When appropriate (i.e., on the water side of the structure), the treated backfill technique (described above) can also be used to minimize off-site movement of termiticide.

#### **EXTERIOR PERIMETER/INTERIOR SPOT TREATMENT\***

\*Not approved for use in Louisiana.

#### **INFORMATION**

Exterior Perimeter/Interior Spot Treatment is an optional method of termite treatment only for use in post-construction applications, after the final grade is established. Structural protection when using the Exterior Perimeter/Interior Spot Treatment is accomplished by: 1) establishing a continuous treated zone around the entire exterior foundation wall of the building; and 2) spot-treating infested areas on the building interior. Soil adjacent to the exterior foundation wall must be treated in the same manner as conventional (full) application. It is required that a complete and continuous treated zone be achieved around the entire exterior perimeter, including under any attached slabs such as garages, porches, patios, driveways and pavement adjoining the foundation. Interior spot treatments must then be made to any indoor areas where termite activity is present. Optional interior spot treatments may also be made to high risk areas including, but not limited to plumbing and utility penetrations (including bath traps), along settlement cracks and expansion joints, and dirt-filled porches.

Exterior Perimeter/Interior Spot Treatment can be used as a preventative treatment (before structural infestation occurs) or as a curative treatment (after structural infestation occurs) in existing structures. Preventative treatment does not include pre-construction applications made to protect construction. It is required that a thorough structural inspection be completed before treatment, to locate all areas of active infestation. Spot treatment of all known sites of termite activity is required with this optional labeling. If no termite activity is observed inside the structure, interior spot treatments are not required. Do not apply at a lower dosage and/or concentration than specified on this label.

#### **EXTERIOR PERIMETER TREATMENT**

It is required that all structures, regardless of the type of construction, be protected by establishing a vertical treated zone along the outer perimeter of the foundation wall. Consult the OUTER FOUNDATION WALLS section of this label (see below) for detailed directions of this treatment procedure.

**1. OUTER FOUNDATION WALLS:** Application must be made by trenching, or where appropriate (see below) by trenching, or trenching and rodding from the bottom of the trench, around the outside of the foundation walls. When trenching, excavate a trench along the outside foundation that is about 6 inches wide and 6 inches deep. Apply 4 gallons of solution (see APPLICATION VOLUME) per 10 linear feet, per foot of depth to provide a uniform vertical treated zone.

- For shallow foundations, one foot or less of depth, dig a narrow trench that does not exceed 6 inches wide and 6 inches deep along the outside of the foundation walls, being careful not to dig below the bottom of the footings. For foundations with exposed footings, dig a trench alongside the footing taking care not to undermine the footing.
- For basements and other foundations deeper than one foot, the application must be made by trenching and rodding from bottom of a shallow trench. When rodding, rod holes must be spaced in a manner that will allow for a continuous treated zone, not to exceed 12 inches, to be deposited along the treated area. Rod holes must not extend below the footing. Rodding depth should be to the top of the footer, or to a maximum depth of 4 feet, or according to state or local regulations.
- For all applications, apply the solution into the trench and mix with the excavated soil as it is replaced into the trench. Use a low-pressure spray to treat soil that will be replaced into the trench after rodding. Mix spray solution with the soil as it is being replaced in the trench.

Where direct access to soil on the outer foundation wall is impossible due to attached porches, entrance platforms, garages and similar slab structures, consult the CONCRETE SLAB-ON-GROUND section of this label for directions on treatment of soil beneath these structures. However, where obstruction (e.g., concrete walkways) adjacent but not attached to foundation, or where soil type and/or conditions prevent trenching the exterior perimeter treatment may be performed at the obstructed location by rodding alone. When rodding, rod holes must be spaced in a manner that will allow for a continuous treated zone, not to exceed 12 inches, to be deposited along the treated area.

**2. CONCRETE SLAB-ON-GROUND:** To treat soil beneath a slab, including attached porches, carports, entrance platforms, garages and similar slab structures abutting the foundation wall, it is necessary to drill through the slab. If an infestation is associated with an expansion joint, crack, utility penetration, or similar access point in the slab, treat by drilling and injecting through the slab. Drill holes must be spaced in a manner that will allow for application of a continuous chemical treated zone but must extend a minimum of 3 feet on both sides of the infested site. Apply 4 gallons of solution (see APPLICATION VOLUME) per 10 linear feet. **DO NOT MAKE TREATMENT UNTIL LOCATION OF HEAT OR AIR CONDITIONING DUCT AND VENTS ARE KNOWN AND IDENTIFIED. USE EXTREME CAUTION TO NOT CONTAMINATE DUCTS AND VENTS.** Plug and fill all drilled holes in commonly occupied areas with suitable sealant. Plugs must be of non-cellulose material.

**3. INACCESSIBLE CRAWL SPACES:** If termite activity is found along the perimeter wall or on a pier within an inaccessible crawl space, areas with termite activity must be treated. Apply 4 gallons of solution (see APPLICATION VOLUME) per 10 linear feet to create a vertical treated zone, which must extend a minimum of 3 feet on both sides of the infested site. Optional directions for horizontal rodding: Treatment may also be made by drilling through the foundation wall (or through the floor above) to treat the soil along the perimeter wall at a rate of 4 gallons of solution (see APPLICATION VOLUME) per 10 linear feet. Drill spacing must be at intervals not to exceed 16 inches. Many states have shorter intervals so check state regulations which may apply. If termite activity is neither along the perimeter wall nor on a pier within the inaccessible crawl space, to prevent subterranean termites from constructing mud tubes between soil in the crawl space and wooden elements in the structure, an overall soil treatment of this product may be applied. Remove all cellulose debris before application. Apply 1 gallon of solution (see APPLICATION VOLUME) per 10 square feet to provide a uniform chemical treated zone.

**4. ACCESSIBLE CRAWL SPACES:** If termite activity is found within a accessible crawl space, the area(s) where termite activity exist must be treated by trenching, or trenching and rodding from the bottom of the trench, along the interior foundation walls, around piers, interior supports in contact with the soil, plumbing, or utility services. Apply 4 gallons of solution (see APPLICATION VOLUME) per 10 linear feet, per foot of depth, to create a vertical treated zone, which must extend a minimum of 3 feet on both sides of the infested site. Rodding may be done from the bottom of a shallow trench to the top of the footing or to a minimum depth of 4 feet. When rodding, rod holes must be spaced in a manner that will allow for a continuous treated zone, not to exceed 12 inches, to be deposited along the treated area. Rod holes must not extend below the footing. When trenching, dig a narrow trench about 6 inches wide and 6 inches deep. Use a low-pressure spray to treat soil which will be placed in the trench, mixing the spray solution with soil as it is being placed in the trench.

**RESTRICTION:** Do not allow people or pets to contact or to reoccupy the contaminated areas of the structure until the clean-up is completed.

## INTERIOR SPOT TREATMENT

Targeted applications must be made to all known infested sites inside the structure. One or more of the following application methods must be used to make interior spot treatments:

- Sub-slab injections made through the slab at or near areas where termites are known to be penetrating the slab to reach

wood in the structure and/or at or near sites of active infestations. Apply 4 gallons per 10 linear feet per foot of depth. Sub-slab injections must extend to a minimum of 3 feet on either side of every known infested site at expansion joints or cracks in slabs.

- Void treatments using injection of sprays, mist or foams into above ground structural voids, termite carton nests, and other infested locations.
- Wood treatments using injection techniques and/or surface applications, to treat active infestations in structural timbers.

To maximize dispersion of treatment solution in soil and in above ground locations, the use of foam and directional dispersion tips is encouraged for all interior spot treatments. Consult section(s) of this label appropriate to the element of construction, FOAM APPLICATIONS or CONTROL OF WOOD INFESTING PESTS for detailed directions on any of these treatment procedures.

**1. INTERIOR SLABS:** When termite activity is located within an interior wall or structural member, the soil beneath the slab and the wall void at this site of activity must be treated. The source of infestation at an expansion joint, crack, through a utility penetration, or similar access point in the slab, must be treated by drilling and injecting through the slab. Drill holes in the slab must be spaced in a manner that will allow for application of a continuous chemical treated zone, which must extend a minimum of 3 feet on either side of the infested site. Apply 4 gallons of solution (see APPLICATION VOLUME) per 10 linear feet. To maximize dispersion of treatment solution in soil, the use of foam and directional dispersion tips is encouraged. To treat the wall void, consult section(s) of this label appropriate to the element of construction, FOAM APPLICATIONS or CONTROL OF WOOD INFESTING PESTS for detailed directions on any of these treatment procedures. DO NOT MAKE TREATMENT UNTIL LOCATION OF HEAT OR AIR CONDITIONING DUCTS AND VENTS ARE KNOWN AND IDENTIFIED. USE EXTREME CAUTION TO NOT CONTAMINATE DUCTS AND VENTS. Plug and fill all drilled holes in commonly occupied areas with suitable sealant. Plugs must be of non-cellulose material or covered by an impervious, non-cellulose material.

**2. HOLLOW BLOCK FOUNDATION OR MASONRY VOIDS:** Termite activity located within hollow-block foundations or masonry voids must be treated. Spot treatment at the site(s) of termite activity must extend a minimum of 3 feet on both sides. Treat masonry voids by applying 2 gallons of solution per 10 linear feet to the lower part of the void so that it reaches the top of the footing or soil. Drill spacing in masonry voids must be at intervals not to exceed 16 inches; states may have shorter intervals so check state regulations which may apply. To maximize dispersion of treatment solution in voids, the use of foam and directional dispersion tips is encouraged. To treat structural voids above sites of termite activity in masonry, consult section(s) of this label appropriate to the element of construction, FOAM APPLICATIONS or CONTROL OF WOOD INFESTING PEST for detailed directions on any of these treatment procedures. Treatment of voids in block or rubble foundation walls must be closely examined. Applicators must inspect areas of possible runoff as a precaution against application leakage in the treated areas. Some areas may not be treatable or may require mechanical alteration prior to treatment. All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site (refer to Use Instructions).

**RESTRICTION:** Do not allow people or pets to contact or to reoccupy the contaminated areas of the structure until the clean-up is completed.

**3. BATH TRAPS:** If termite activity is observed within 2 feet of the bath trap, then exposed soil or soil covered with tar or similar type of sealant around plumbing and/or drainpipe entry areas must be treated. Tar or sealant may have to be removed to allow for adequate soil treatment. An access door or inspection portal should be installed if one is not present. After inspection and removal of any wood or cellulose debris, the soil can be treated by rodding or drenching the soil at the volume of no less than 3 gallons of solution per square foot.

**4. SHOWER OR FLOOR DRAINS:** If termite activity is observed within 2 feet of a shower or floor drain in the slab, the soil beneath the drain must be treated. Drill through the slab adjacent to the drain and use sub-slab injection to apply solution to the soil. Multiple access points may be drilled adjacent to the drain. Treat soil at a volume of 1 gallon of solution per square foot.

## FOAM APPLICATIONS

Construction practices, soil subsidence and other factors may create situations in which a continuous chemical treated zone cannot be achieved using conventional treatment alone. In situations where necessary, conventional application methods can be supplemented through use of foam generating equipment, or similar devices, to provide a continuous treated zone.

Foam application may be made alone or in combination with conventional application methods, provided that the labeled amount of active ingredient per unit area is used.

**Foam Application Use Directions:** Mix appropriate concentration of IMI 2 LB INSECTICIDE in water and add the manufacturer's recommended quantity of foam agent to the IMI 2 LB INSECTICIDE solution (see table for foaming recommendations). Apply a sufficient volume of IMI 2 LB INSECTICIDE foam alone or in combination with liquid solution to provide a continuous treated zone at the labeled rate for specific application sites.

NOTE: Add the manufacturer's recommended quantity of foam agent to the IMI 2 LB INSECTICIDE solution.

[Only one of the tables below will be used based upon the size of container offered for sale]

[FOR 240 ML SIZE ONLY]

**MIXING TABLE - IMI 2 LB INSECTICIDE FOAM**

IMI 2 lb. (mL)	GALLONS OF WATER	FOAM EXPANSION RATIO	FINISHED FOAM (0.05% ai)
160	1	20:1	20 gal
80	1	10:1	10 gal
40	1	5:1	5 gal

[FOR 55 FL OZ SIZE ONLY]

**MIXING TABLE - IMI 2 LB INSECTICIDE FOAM**

IMI 2 lb (fl oz)	GALLONS OF WATER	FOAM EXPANSION RATIO	FINISHED FOAM (0.05% ai)
6.9	1	25:1	25 gal
	2.5	10:1	
	5	5:1	
13.8	1	50:1	50 gal
	2.5	20:1	
	5	10:1	

Depending on the circumstances, foam applications may be used alone or in combination with liquid solution applications. Applications may be made behind veneers, piers, chimney bases, into rubble foundations, into block voids or structural voids, wall voids, under slabs, stoops, porches, or to the soil in crawlspaces, and other similar voids.

Foam and liquid applications must be consistent with volume and active ingredient instructions in order to ensure proper application has been made. The volume and amount of active ingredient are essential to an effective treatment. At least 75% of the gallons of IMI 2 LB INSECTICIDE must be applied as a typical liquid treatment. The remaining 25% or fewer gallons is delivered to appropriate locations using a foam application.

NOTE: When foam is used solely to kill subterranean termites in above ground locations (such as feeding galleries in wooden framing, or in voids with framed walls), and whenever the target pest is other than subterranean termites (drywood termites, beetles, ants, etc.) dilute solutions of IMI 2 LB INSECTICIDE may be expanded by foaming without concentrating the IMI 2 LB INSECTICIDE solution as previously described for soil applications. Add the manufacturers' recommended volume of foaming agent to produce foam of the desired expansion ratio. Use application tips and methods suitable to the site and pest.

**CONTROL OF WOOD INFESTING PESTS**

For control of above ground termites and carpenter ants in localized areas, apply a 0.05 to 0.1% solution of sufficient volume of IMI 2 LB INSECTICIDE foam to voids and galleries in damaged wood, and in spaces between wooden structural members and between the sill plate and foundation where wood is vulnerable. Applications may be made to inaccessible areas by drilling, and then injecting the suspension or foam with a suitable directional injector into the damaged wood or wall voids. Termite carton nests in building voids may be injected with a 0.05 to 0.1% suspension or foam. Multiple injection points to varying depths may be necessary. It is desirable to physically remove carton nest material from building voids when such nests are found. Application to attics, crawl spaces, unfinished basements, or man-made voids may be made with a coarse fan spray of 0.05 to 0.1% solution or foam to control exposed worker and winged reproductive forms of termites or carpenter ants. This type of application is intended to be a supplemental treatment for control of above ground subterranean termites and carpenter ants.

It is recommended to remove or prune away any shrubbery, bushes, and tree branches touching the structure. Vegetation touching the structure may offer a route of entry for ants into the structure. This may allow ants to inhabit the structure without coming in contact with the treatment. If nests are found, direct treatment of IMI 2 LB INSECTICIDE can be made to these nests.

Use a 0.05% to 0.1% solution to control existing infestations or to prevent infestation by termites or carpenter ants in trees, utility poles, fencing and decking materials, landscape timbers and similar non-structural wood-to-soil contacts. If possible, locate the interior infested cavity and inject a 0.05 to 0.1% solution or sufficient volume of IMI 2 LB INSECTICIDE foam using an appropriate treatment tool with a splash back guard. These non-structural wood-to-soil contacts may also be treated by applying a solution to the soil as a spot application or continuous treated zone applied as a drench or by rodding around the base of the point(s) of soil contact(s). Rod holes should be placed approximately 3 inches away from the soil contact point(s) and spaced no more than 12 inches along the

perimeter of the soil contact(s). For small poles or posts (< 6 inches in diameter), apply 1 gallon per foot of depth. For larger constructions, apply 4 gallons per 10 linear feet per foot of depth. Retreat as needed to maintain protection.

Termite carton nests in trees may be injected with a 0.05 to 0.1% solution or sufficient volume of foam using a pointed injection tool. Multiple injection points to varying depths may be necessary. Removal of carton material from trees is desirable but may not be necessary when foam application is used. In some instances, a perimeter application of a 0.05% to 0.1% solution applied to soil around the root flare of the tree may be necessary to prevent reinfestation by termites in the soil. For small trees (< 6 inches in diameter), apply 1 gallon of solution. For larger trees, apply 4 gallons per 10 linear feet (measured as the circumference at the root flare).

**Drywood termites and wood-infesting beetles or borers** (such as, but not limited to, powder post beetles, anobiid or deathwatch beetles, false powder post beetles, old house borers, wharf borers, or ambrosia or bark beetles). **Galleries and structure voids** can be treated with sprays, mists, or foams of a 0.05% to 0.1% IMI 2 LB INSECTICIDE solution. Locate galleries by using visual signs (frass or pellets, blistered wood, emergence or clean out holes), the presence of live insects, mechanical sounding techniques, or listening devices (e.g., stethoscopes, acoustic emission detectors). Penetrate the gallery system by drilling holes to receive the injector tip or treatment tool. Distribute drill holes to adequately cover the gallery system. [NOTE: Avoid drilling where electrical wiring, plumbing lines, etc. are located.] Apply IMI 2 LB INSECTICIDE solutions as a low pressure (about 20 psi) spray or by misting or, where appropriate, by foaming. It is not necessary to treat to the point where runoff is detected from adjacent holes. ] NOTE: Do not apply where electrical shock hazards exist.] Drill holes should be sealed after treatment. Also, **wood surfaces** can be sprayed or misted with a 0.05% to 0.1% solution or, where appropriate, use a sufficient volume of foam. For inaccessible surfaces, drill and treat the interior of structural voids. Surfaces treated may include exposed wooden surfaces in crawlspaces, basements, or attics, wooden exterior surfaces such as decks, fencing, or siding, structural voids, channels in damaged wood, in spaces between wooden members of a structure, and junctions between wood and foundations. Apply by brushing or as a coarse, low pressure (about 20 psi) spray to the wood surface; apply sufficient volume to cover the surface to the point of wetness, but avoid applying to the point of runoff. When spraying overhead in living areas, cover surfaces below the treated area with plastic sheeting or similar material, avoid contact with treated surfaces until spray deposits have dried. Retreat as needed to maintain protection.

**Localized treatment for carpenter bees:** Apply a 0.05% to 0.1% solution as a spray or mist, or sufficient volume of foam, directly into gallery entrance holes. Following treatment, entrance holes may be plugged with small pieces of steel wool or similar material.

## RETREATMENT

Retreatment for subterranean termites can only be performed if there is clear evidence of reinfestation, disturbance, or disruption of the treated zone due to construction, foundation repair, plumbing repair, excavation, or landscaping and/or evidence of the breakdown of the termiticide treated zone in the soil. The vulnerable or reinfested areas may be retreated in accordance with application techniques described in this product's labeling. The timing and type of these retreatments will vary, depending on factors such as termite pressure, soil types, soil conditions and other factors which may reduce the effectiveness of the treated zone. Retreatment may be made as either a spot or complete treatment.

When a structure is not known to be reinfested and the treated zone is not disturbed, but where the structure was last treated five or more years ago, retreatment may be performed if, in the judgment of the applicator, it is necessary to ensure adequate protection of the structure. In determining the timing of any retreatment, the applicator should consider efficacy and/or degradation data and/or site-specific conditions and previous experience that indicate a vulnerability of the structure to termite attack.

**Annual retreatment of the structure is prohibited unless there is clear evidence that reinfestation or treated zone disruption has occurred.**

When another registered termite control product/system is used as the primary treatment for prevention or control of subterranean termites and is applied to all label-specified areas, IMI 2 LB INSECTICIDE may be applied as a spot application in a secondary treatment to critical areas of the structure including plumbing and utility entry sites, bath traps, expansion joints, foundation cracks or areas where the foundation has been removed/disturbed. The outside foundation wall, and areas of known or suspected activity at either a pre-construction or post-construction timing. These secondary treatments must be applied in amounts and concentration in accordance with label directions relevant to the treatment area(s) to receive the secondary treatment.

## PERIMETER PEST CONTROL

**For control of ants in houses and other structures,** apply a 0.05 to 0.1% solution as a general surface, spot crack and crevice or wall void application. Apply to surfaces on buildings, porches, patios and other structures, around doors and windows, eaves or attic vents. Utility entry points, soffit areas and other exterior openings (including foundation cracks or drilled holes) where the pests enter the structure or where they crawl or hide. Spray into cracks and crevices. Spray, mist or foam into voids where these ants or their nests are present. Apply the volume of spray mist or foam sufficient to cover the area, but do not allow excessive dripping or run-off to occur from vertical or overhead surfaces.

Treat soil, turf or ground cover adjacent to the structure where ants are trailing or may find food or harborage. Apply to flower, shrub or ornamental plant beds adjacent to the structure where ants may find food or forage. To control ants tunneling in soil apply a 0.05% to 0.1% solution as a drench or soil injection at intervals to establish a continuous treated zone. Treat along the edge of walls, driveways

or other hard surfaces where ants are tunneling beneath the surface.

Aerial Nests: If ant nests are located in tree hollows or non-structural wooden construction (e.g.; posts, fences, decks) treat the interior cavity and/or the nest site by injecting a 0.05%-0.01% solution as a spray mist, or sufficient volume of foam.

Apply in sufficient water to cover the foliage and soil area being treated. Maximum application is once per month to maintain control.

Do not allow residents or pets into the immediate area during the application or contact with treated areas until spray has dried. Interior applications for ant control are limited to spot, crack and crevice, or wall void applications only.

Do not use this product against native or imported fire ants, pharaoh or harvester ants.

**NOTE:** In instances of high pest pressures and quick knockdown or elimination at pest entry points is needed, additional treatments using IMI 2 LB INSECTICIDE with targeted applications of a pyrethroid such as TEMPO® SC ULTRA or SUSPEND®SC to doors and windows, utility entry points, and other places where these pests enter the structure may be made. Read and follow all label directions for use of this companion product.

## RESTRICTIONS

- After treatment, plug and fill all holes drilled in concrete slab areas of the building with a suitable sealant.
- Do not apply solution until location of heat pipes, ducts, water and sewer lines and electrical conduits are known and identified. Caution must be taken to avoid puncturing and injection into the structural elements.
- Do not plant for the purpose of consumption, edible plants into the treated areas of soil.
- Do not contaminate public and private water supplies.
- Use anti-backflow equipment or an air gap on filling hoses.
- Consult State, Federal, or local authorities for information regarding the approved treatment practices for areas in close proximity to potable water supplies.

## APPLICATION ON TURFGRASS

IMI 2 LB INSECTICIDE may be used to control listed insect pests on turf grass in home lawns, business and office complexes, shopping complexes, multi-family residential complexes, golf courses, airports, cemeteries, parks, playgrounds, and athletic fields. This product may not be used on sod farms.

IMI 2 LB INSECTICIDE controls the following soil inhabiting pests: Northern & Southern masked chafers, *Cyclocephala borealis*, *C. immaculata*, and/or *C. lurida*; Asiatic Garden beetle, *Maladera castanea*; European chafer, *Rhizofrogus majalis*; Green June beetle, *Cotinis nitida*; May or June beetle, *Phyllophaga* spp.; Japanese beetle, *Popillia japonica*; Oriental beetle, *Anomala orientalis*; Billbugs, *Spherophorus* spp.; Annual bluegrass weevil, *Hyperodes* spp.; Black turfgrass atenioid, *Ataenius spretulus* and *Aphodius* spp. European Crane Fly *Tipula paludosa*, and mole crickets, *scapteriscus* spp. IMI 2 LB INSECTICIDE can also be used for suppression of cutworms and chinch bugs.

For optimum control, make applications preceding or during the egg laying period of the target pest. The active ingredient in IMI 2 LB INSECTICIDE has enough residual activity so that applications can be made preceding the egg laying activity. Application timing can be based on historical monitoring of the site, previous records or experiences, current season adult trapping or other methods. Most favorable control will be achieved when applications are made prior to egg hatch of the target pests, followed by sufficient irrigation or rainfall to move the active ingredient through the thatch.

Do not make applications when turfgrass areas are waterlogged or the soil is saturated with water. Sufficient distribution of the active ingredient cannot be achieved under these conditions. The treated turf area must be in such a condition that the rainfall or irrigation will penetrate vertically in the soil profile. Applications cannot exceed a total of 1.6 pints (0.4 lb of active ingredient) per acre per year.

## APPLICATION EQUIPMENT FOR USE ON TURFGRASS

Apply IMI 2 LB INSECTICIDE in sufficient water to provide adequate distribution in the treated area. The use of accurately calibrated equipment normally used for the application of turfgrass insecticides is required. Use equipment which will produce a uniform, coarse droplet spray, using a low pressure setting to eliminate off target drift. Check calibration periodically to ensure that equipment is working properly.

Do not apply through any irrigation system.

## APPLICATIONS

### TURF GRASSES

PEST	RATE	APPLICATION INSTRUCTIONS
Larvae of: Annual bluegrass weevil Asiatic garden beetle Billbug Black turf grass ataenius Cutworms (suppression) European chafer European crane fly Green June Beetle Japanese beetle Northern Masked chafer Oriental beetle <i>Phyllophaga</i> spp. Southern masked chafer	1 .25 pt/A or 0.46 fl. oz. (14 mL) per 1000 sq. ft.	For best control of grubs, billbugs, annual bluegrass weevil, and European Crane Fly, apply prior to egg hatch of the target pest. Read <b>APPLICATION EQUIPMENT</b> section of this label.
Chinch bugs (suppression) Mole crickets	1.6 pt /A or 0.6 fl. oz. (17 mL) per 1000 sq. ft.	For suppression of chinch bugs, apply before hatching of the first instar nymphs.  To control mole crickets, apply before or during the peak egg hatch period.  Follow label instructions for other insecticides if tank-mixing.

Consult your local turf, state Agricultural Experiment Station, or State Extension Service Specialists for more specific information regarding timing of application.

#### Restrictions

- Irrigation or rainfall must occur within 24 hours after application to move the active ingredient through the thatch.
- Do not apply more than 1.6 pt (0.4 lb of active ingredient) per acre per year.
- Do not mow turf or lawn area until after sufficient irrigation or rainfall has occurred so that uniformity of application will not be affected.
- Do not allow this product to contact plants in bloom if bees are foraging in the treatment area.

## APPLICATION TO ORNAMENTALS

IMI 2 LB INSECTICIDE is for use on ornamentals in commercial and residential landscapes and interior plantscapes. IMI 2 LB INSECTICIDE is a systemic product and will be taken up into the plant system from root uptake. To assure optimum effectiveness, the product must be placed where the growing portion of the target plant can absorb the active ingredient. The addition of a nitrogen containing fertilizer, where applicable, into the solution may enhance the uptake of the active ingredient. Application can be made by foliar application or soil applications; including soil injection, drenches, and broadcast sprays. Foliar applications offer locally systemic activity against insect pests.

When making soil applications to plants with woody stems, systemic activity will be delayed until the active ingredient is taken up throughout the plant. In some cases, this translocation delay could take 60 days or longer. For this reason, treat prior to anticipated pest infestation to achieve optimum levels of control.

For outdoor ornamentals, applications cannot exceed a total of 1.6 pints (0.4 lb of active ingredient) per acre per year.

#### Ant Management Programs

Use IMI 2 LB INSECTICIDE to control aphids, scale insects, mealybugs and other sucking pests on ornamentals to limit the honeydew available as a food source for ant populations. IMI 2 LB INSECTICIDE applications can then be supplemented with residual sprays, bait placements or other ant control tactics to further reduce the pest population.



**Not for use in commercial greenhouses, nurseries, or on grass grown for seed, or on commercial fruit and nut trees.**

**Do not apply this product, by any application method to linden, basswood, or other Tilia species.**

**APPLICATION EQUIPMENT FOR FOLIAR APPLICATIONS**

IMI 2 LB INSECTICIDE mixes readily with water and may be used in many types of application equipment. Mix product with the required amount of water and apply as desired dependent upon the selected use pattern.

When making foliar applications on hard to wet foliage such as holly, pine, or ivy, the addition of a spreader/ sticker is recommended. If concentrate or mist type spray equipment is used, an equivalent amount of product must be used on the area sprayed, as would be used in a dilute application.

IMI 2 LB INSECTICIDE has been found to be compatible with commonly used fungicides, miticides, liquid fertilizers, and other commonly used insecticides. Check physical compatibility using the correct proportion of products in a small jar test if local experience is unavailable.

Do not apply through any irrigation system.

**APPLICATIONS**

**FOR USE ONLY IN AND ON INDUSTRIAL AND COMMERCIAL BUILDING SITES AND RESIDENTIAL AREAS.**

SITE	PEST	RATE	APPLICATION INSTRUCTIONS
Trees Shrubs Evergreens Flowers Foliage plants Groundcovers Interior plantscapes	Adelgids Aphids Japanese beetles Lace bugs Leaf beetles (including elm and viburnum leaf beetles) Leafhoppers (including glassy-winged sharpshooter) Mealybugs Planthoppers (Including Spotted lantern fly) Psyllids Sawfly Larvae Thrips (suppression)	1.5 fl. oz. (45 mL) per 100 gal of water	<b>Foliar Applications:</b> Begin applications before the onset of high pest populations and reapply as needed.
	White grub larvae (such as Japanese beetle larvae, Chafers, Phyllophaga spp. Asiatic garden beetle, Oriental beetle) Planthoppers (Including Spotted lantern fly)	0.46 to 0.6 fl. oz. (14 to 17 mL) <sup>1</sup> per 1000 sq. ft.	<b>Broadcast Applications:</b> Use enough water to mix the product and thoroughly apply to the treatment area. Do not use less than 2 gallons of water per 1000 sq ft. Irrigate after application to incorporate IMI 2 LB INSECTICIDE into the upper soil layer.  For additional use directions, refer to the <b>FLOWERS and GROUND COVERS</b> section of this label.

<sup>1</sup> Use higher rate within range when infestations are severe

**SOIL INJECTION\* AND SOIL DRENCH APPLICATIONS IN AND ON INDUSTRIAL AND COMMERCIAL BUILDING SITES, RESIDENTIAL AREAS, AND STATE, NATIONAL AND PRIVATE WOODED AND FORESTED AREAS.**

\*No Soil injection Applications Allowed in Nassau or Suffolk Counties of New York.

\*Do not apply more than 1.6 pints (0.4lb of active ingredient per acre per year

PEST	SITE/RATE	APPLICATION INSTRUCTIONS	REMARKS
Adelgids Aphids Armored scales (suppression) Black vine weevil Larvae Eucalyptus longhorned borer Flatheaded borer (including bronze birch, emerald ash borer and alder borer) Japanese beetles Lace bugs Leaf beetles (including elm and viburnum leaf beetles) Leafhoppers (including glassy- winged sharpshooter) Leafminers Mealybugs Pine tip moth larvae Planthoppers (Including Spotted lantern fly) Psyllids Royal palm bugs Sawfly larvae Soft scales Thrips (suppression) White grub larvae Whiteflies	<p><b>TREES</b></p> <p>0.1 to 0.4 fl. oz. (3 to 12 mL)<sup>1</sup> per inch of trunk diameter (D.B.H.)</p> <p>Use the higher rate (0.3-0.4 fl oz) only for trees greater than 15 DBH to control the following pests: Emerald Ash borer, Eucalyptus longhorned borer, Bronze birch borer and Alder borer.</p>	<p><b>SOIL INJECTION:</b></p> <p><b>Grid System:</b> Space holes in a grid pattern on 2.5 foot centers, extending to the drip line of the tree.</p> <p><b>Circle System:</b> Apply in holes evenly spaced in circles, (use more than one circle dependent upon the size of the tree) beneath the drip line of the tree extending in from that line.</p> <p><b>Basal System:</b> Space injection holes evenly around the base of the tree trunk no more than 6 to 12 inches out from the base.</p> <p><b>Soil Drench:</b> Apply uniformly as a drench around the base of the tree in not less than 10 gallons of water per 1000 square feet. Direct application to the root area. Remove plastic or any other barrier that will stop solution from reaching the root zone.</p>	<p>Use enough water to mix the product and inject an equal amount of solution in each hole. Use low pressure and sufficient solution for distribution of the liquid into the treatment area. Keep the treated area moist for 7 to 10 days.</p> <p>Do not use less than 4 holes per tree.</p> <p><b>For Control of Specified Borers:</b> Trees with existing insect damage and stress may not recover after treatment with IMI 2 LB INSECTICIDE.</p>
	<p><b>SHRUBS</b></p> <p>0.1 to 0.2 fl. oz. (3 to 6 mL)<sup>1</sup> per foot of shrub height</p>	<p><b>Soil Injection:</b> Apply at the labeled dosage to each plant.</p> <p><b>Soil Drench:</b> Apply uniformly as a drench around the base of the tree in not less than 10 gallons of water per 1000 square feet. Direct application to the root area. Remove plastic or any other barrier that will stop solution from reaching the root zone.</p>	<p>Use enough water to mix the product and inject an equal amount of solution in each hole. Use low pressure and sufficient solution for distribution of the liquid into the treatment area. Keep the treated area moist for 7 to 10 days.</p> <p>Do not use less than 4 holes per shrub.</p>
	<p><b>FLOWERS AND GROUNDCOVERS</b></p> <p>0.46 to 0.6 fl. oz. (14 to 17 mL)<sup>1</sup> per 1000 sq. ft</p>	<p>Apply as a broadcast treatment before or after planting or apply prior to bloom or after all flower petals have fallen off for established plants. Mix into soil. Irrigate thoroughly after application.</p>	

<sup>1</sup> Use higher rate within range when infestations are severe

**FOLIAR APPLICATIONS FOR USE ONLY IN AND ON RESIDENTIAL AREAS**

SITE	PEST	RATES	APPLICATION INSTRUCTIONS
<b>POME FRUITS</b> <b>Apple</b> <b>Crabapple</b> <b>Loquat</b> <b>Mayhaw</b> <b>Pear</b> <b>Pear (oriental)</b> <b>Quince</b>	<b>Aphids (except Woolly apple aphid)</b> <b>Leafhoppers (including glassy-winged sharpshooter)</b> <b>Leafminer</b> <b>Mealybugs*</b> <b>Planthoppers (Including Spotted lantern fly)</b> <b>San Jose scale*</b>	1.5 fl oz (45 mL) per 100 gal or 6.0 fl oz/A <sup>1</sup>	<p>Apply labeled dosage as foliar spray as needed after petal-fall is complete.</p> <p>For control of rosy apple aphid, apply prior to leafrolling caused by the pest.</p> <p>For first generation leafminer control, make first application as soon as petal-fall is complete. Greatest leafminer control will result from the earliest possible application. For second and succeeding generations of leafminer, optimal control is obtained from applications made early in the adult flight against egg and early instar larvae. A second application may be required 10 days later if severe pressure continues or if generations are overlapping. A single application may result in suppression only. IMI 2 LB INSECTICIDE will not control late-stage larvae.</p> <p>For San Jose Scale, time applications to the crawler stage. Treat each generation.</p> <p>For late season (preharvest) control of leafhopper species, apply IMI 2 LB INSECTICIDE while most leafhoppers are in the nymphal stage.</p> <p>For control of mealybugs, ensure good spray coverage of the trunk and scaffolding limbs or other resting sites of the mealybug.</p> <p>Do not apply more than 6.0 fluid ounces per acre in a single application. Do not make more than 5 applications.</p> <p>Allow 10 or more days between applications. Allow at least 7 days between last application and harvest.</p> <p>* Not for use in California for control on pears.</p>
<b>Pecan*</b>	<b>Yellow pecan aphid</b> <b>Black margined aphid</b> <b>Pecan leaf phylloxera</b> <b>Pecan spittlebug</b> <b>Pecan stem phylloxera</b> <b>Planthoppers (Including Spotted lantern fly)</b>	1.5 fl. oz. (45 mL) per 100 gal or 6.0 fl. oz./A <sup>1</sup>	<p>Make foliar applications as pests begin to build before populations become extreme. Two applications at a 10 to 14 day interval may be required to achieve control. Scout and retreat if needed.</p> <p>Thorough uniform coverage of foliage is necessary for optimal control. Addition of an organosilicone-based spray adjuvant at a rate not to exceed the adjuvant manufacturer's specified use rate may improve coverage.</p> <p>Do not apply more than a total of 18.0 fluid ounces of IMI 2 LB INSECTICIDE per acre per year. Do not make more than 3 applications.</p> <p>Allow 10 or more days between applications.</p> <p>* Use on pecans not permitted in California unless directed by state specific 24(c) supplemental labeling.</p>

<sup>1</sup> The amount of IMI 2 LB INSECTICIDE required per acre will depend on tree size and volume of foliage present. The rate per acre is based on a standard of 400 gallons of dilute spray solution per acre for large trees.

**FOLIAR APPLICATIONS FOR USE ONLY IN AND ON INDUSTRIAL AND COMMERCIAL BUILDING SITES AND RESIDENTIAL AREAS.**

CROP	PEST	RATE	APPLICATION INSTRUCTIONS
Grapes	Leafhoppers (including glassy-winged sharpshooter) Mealybugs Planthoppers (Including Spotted lantern fly)	1.5 fl. oz. (45 mL) per 100 gal or 3.0 fl. oz/A (90 mL/A)	Apply specified dosage as a foliar spray using 200 gallons of water per acre. Do not apply more than a total of 6.0 ounces of IMI 2 LB INSECTICIDE per acre per year.  Allow at least 14 days between applications. Applications may be applied up to and including day of harvest.

**RESTRICTIONS**

- Do not graze treated areas or use clippings from treated areas for feed or forage.
- Avoid runoff or puddling of irrigation water following application. Keep children and pets off treated area until dry.
- Do not apply IMI 2 LB INSECTICIDE to areas which are water logged or saturated, which will not allow penetration into the root zone of the plant.
- Do not apply more than 1.6 pt (0.4 lb of active ingredient) per acre per year.
- Do not apply this product, by any application method to linden, basswood, or other *Tilia* species.

Treated areas may be replanted with any crop specified on an imidacloprid label, or with any crop for which a tolerance exists for the active ingredient.

For crops not listed on an imidacloprid label, or for crops for which no tolerances for the active Ingredient have been established, a 12-month plant-back interval must be observed.

**STORAGE AND DISPOSAL**

Do not contaminate water, food or feed by storage or disposal.

**Pesticide Storage and Spill Procedures:** Store upright at room temperature. Avoid exposure to extreme temperatures. In case of spillage or leakages, soak up with an absorbent material such as sand, sawdust, earth, Fuller's earth, etc. Dispose of with chemical waste.

**Pesticide Disposal:** Pesticide, spray mixture or rinse water that cannot be used according to label instructions must be disposed of at or by an approved waste disposal facility.

**Container Handling Disposal:**

**For Containers equal to or less than 5 Gallons:** Nonrefillable container. Do not reuse or refill this container. Clean container promptly after emptying. Triple rinse as follows: Empty the remaining contents into application equipment or a mix tank and drain for 10 seconds after the flow begins to drip. Fill the container ¼ full with water and recap. Shake for 10 seconds. Pour rinsate into application equipment or a mix tank or store rinsate for later use or disposal. Drain for 10 seconds after the flow begins to drip. Repeat this procedure two more times. Offer for recycling if available. If recycling is not available: then dispose of container in sanitary landfill.

**For Containers greater than 5 Gallons:** Nonrefillable container. Do not reuse or refill this container. Clean container promptly after emptying. Triple rinse as follows: Empty the remaining contents into application equipment or a mix tank. Fill the container 1/4 full with water. Replace and tighten closures. Tip container on its side and roll it back and forth, ensuring at least one complete revolution, for 30 seconds. Stand the container on its end and tip it back and forth several times. Turn the container over onto its other end and tip it back and forth several times. Empty the rinsate into application equipment or a mix tank or store rinsate for later use or disposal. Repeat this procedure two more times. Offer for recycling if available. If recycling is not available: then dispose of container in sanitary landfill.

**For Bulk containers: (Refillable Container)** Refill this container with pesticides only. Do not reuse this container for any other purpose. Cleaning the container before final disposal is the responsibility of the person disposing of the container. Cleaning before refilling is the responsibility of the re-filler. To clean the container before final disposal, empty the remaining contents from this container into application equipment or mix tank. Fill the container about 10 percent full with water. Agitate vigorously or re-circulate water with the pump for 2 minutes. Pour or pump rinsate into application equipment or rinsate collection system. Repeat this procedure two more times.

**IMPORTANT: READ BEFORE USE**

Read the entire Directions for Use, Conditions, Disclaimer of Warranties and Limitations of liability before using this product.

If terms are not acceptable, return the unopened product container at once. By using this product, user or buyer accepts the following conditions, disclaimer of warranties and limitations of liability.

CONDITIONS: The directions for use of this product are believed to be adequate and must be followed carefully. However, because of manner of use and other factors beyond Control Solutions control it is impossible for Control Solutions, Inc. to eliminate all risks associated with the use of this product. As a result, crop injury or ineffectiveness is always possible. All such risks shall be assumed by the user or buyer.

DISCLAIMER OF WARRANTIES: TO THE EXTENT ALLOWED BY APPLICABLE LAW, CONTROL SOLUTIONS, INC. MAKES NO OTHER WARRANTIES, EXPRESS OR IMPLIED, OF MERCHANTABILITY OR OF FITNESS FOR A PARTICULAR PURPOSE OR OTHERWISE, THAT EXTEND BEYOND THE STATEMENTS MADE ON THIS LABEL. No agent of Control Solutions, Inc. is authorized to make any warranties beyond those contained herein or to modify the warranties contained herein. To the extent consistent with applicable law, Control Solutions, Inc. disclaims any liability whatsoever for special, incidental or consequential damages, resulting from the use or handling of this product.

LIMITATIONS OF LIABILITY: TO THE EXTENT ALLOWED BY LAW, THE EXCLUSIVE REMEDY OF THE USER OR BUYER FOR ANY AND ALL LOSSES, INJURIES OR DAMAGES RESULTING FROM THE USE OR HANDLING OF THIS PRODUCT, WHETHER IN CONTRACT, WARRANTY, TORT, NEGLIGENCE, STRICT LIABILITY OR OTHERWISE, SHALL NOT EXCEED THE PURCHASE PRICE PAID, OR AT CONTROL SOLUTIONS, INC.'S ELECTION, THE REPLACEMENT OF PRODUCT.

#### **Additional/ Alternate Marketing Claims**

- *Contains imidacloprid [a chloronicotinyl insecticide] [ a neonicotinoid insecticide]*