# RESTRICTED USE PESTICIDE

# DUE TO ACUTE INHALATION TOXICITY OF HIGHLY TOXIC PHOSPHINE GAS

For retained to and use only by Certified Applicators for those uses covered by the applicators certification or persons trained in accordance with the INVENTA Corporation Applicator's Manual working under the direct supervision and in the physical presence of the Certified Applicator. Physical presence means on site or on premises. Read and follow the label and the INVENTA Corporation Applicator's Manual which contains complete instructions for safe use of this pesticide.

# Quik-Fume

# Aluminum Phosphide Furnigant

A furrigant for use against list insects which infest listed raw Agricultural Commodities, Specified Processed Foods, and Animal Feeds

PRECAUCION AL USUARIO: Si usted no lee ingles, no use este producto hasta que la etiqueta se le haya sido explicado amliamente.



# KEEP OUT OF REACH OF CHILDREN DANGER - PELIGRO - POISON



# PRACTICAL TREATMENT STATEMENT

SYMPTOMS of overexposure to phosphine are headache, dizziness, nausea, difficult breathing, vomiting and diarrhea. In all cases of overexposure, get immediate medical attention. Take the victim to a doctor or emergency treatment facility.

if the gas from aluminum phosphide is INHALED: Move exposed person to fresh air. Keep person warm and make sure person can breathe freely. If breathing has stopped, give artificial respiration by mouth to mouth or other means of resuscitation. Do not give anything by mouth to an unconscious person.

If aluminum phosphide powder, granules, pellets or tableis are SWALLOWED: Drink or administer one or two glasses of water and induce vomiting by touching back of throat with finger, or if available, syrup of ipecac. Do not give anything by mouth if victim is unconscious or not alert.

If powder, granules, or tablets of aluminum phosphide get on SKIN: Brush material of clothes and shees in a well ventilated area. Allow clothes to aerate in a ventilated area prior to laundering. Wash contaminated bare skin thoroughly with soap and water.

If in EYES: Flush with plenty of water. Get medical attention immediately.

# SEE SIDE PANELS FOR ADDITIONAL PRECAUTIONARY STATEMENTS

Net Weight \_\_\_\_\_ Contents \_\_\_\_\_ Manufactured by: INVENTA Corporation, Division of United Phosphorus Worll Bombay, INDIA 400 018

Manufactured for: INVENTA Corporation, 14 Phoenix Drive, Mendham, NJ 07945

E.P.A. Registration No.

E.P.A. Establishment No. 41876-IY-1

IC Revision 880225 Tablets

ACCEPTED 59209-1

UNDER THE FFETPAL INCECTICIDE FUNGICIDE AND HOLD, PROCIDE ACT FOR ECTST MIC FOR REGISTERED UNDER NOT THE SUBJECT TO ATTACKED COMMENTS.

# HUMAN HAZARD PRECAUTIONARY STATEMENTS KEEP OUT OF REACH OF CHILDREN DANGER - PELIGRO - DANGER

DANGER: Aluminum phosphide powder, granules or tablets may be fatal if swallowed. Do not get in eyes, on skin or on clothing. Do not eat, drink or smoke while handling aluminum phosphide furnigants. If a sealed container is opened, or if the material comes into contact with moisture, water or acids, extremely toxic phosphine gas will be released. If a garlic odor is detected, refer to the APPLICATOR AND WORKER EXPOSURE Section of the INVENTA Corporation Applicator's Manual for appropriate monitoring procedures. Pure phosphine gas is odorless; the odor is due to a contaminant. Since an odor may not be detected under certain circumstances, the absence of a garlic odor does not mean that phosphine gas is absent. Observe proper application, aeration, reentry and disposal procedures specified elsewhere in the labeling to prevent overexposure.

# **NOTE TO PHYSICIAN:**

Aluminum phosphide granules, powder, or tablets react with moisture in the air, acids, and many other liquids to release phosphine gas. Mild exposure by inhalation causes malaise, ringing of ears, fatigue, nausea, and pressure in the chest which is relieved by removal to fresh air.

Moderate poisoning causes weakness, vomiting, epigastric pain, chest pain, diarrhea and dyspnea.

Severe poisoning may occur in a few hours to several days, resulting in pulmonary edema and may lead to dizziness, cyanosis, unconsciousness, and death.

In sufficient quantity, phosphine affects the liver, kidneys, lungs, nervous system: and circulatory system. Inhalation can cause lung edema and hyperemia, small perivascular brain hemorrhages, and brain edema. Ingestion can cause lung and brain symptoms, but damage to the viscera is more common. Phosphine poisoning may result in (1) pulmonary edema; (2) liver elevated serum GOT, LDH and alkaline phosphatase, reduced prothrombin, hemorrhage and jaundice; and (3) kidney hematuria and anuria. Pathology is characteristic of hypoxia. Frequent exposure over a period of days or weeks may cause poisoning. Treatment is symptomatic. For further information, contact the nearest National Poison Control Center.

# **ENVIRONMENTAL HAZARDS**

This product is very highly toxic to wildlife. Non-target organisms exposed to phosphine gas in burrows will be killed. Do not apply directly to water or wetlands (swamps, bogs, marshes, and potholes). Do not contaminate water by cleaning of equipment or disposal of wastes.

ENDANGERED SPECIES RESTRICTIONS - Refer to INVENTA Corporation Applicator's Manual

# PHYSICAL AND CHEMICAL HAZARDS

Aluminum phosphide in tablets, pellets, and partially spent dust will release phosphine gas if exposed to moisture from the air or if it comes into contact with water, acids and many other liquids. Piling of tablets, pellots, or dust from their fragmentation may cause a temperature increase and confine the release of gas so that ignition could occur.

Always open containers of aluminum phosphide products outdoors or indoors, in the presence of appropriate mechanical ventilation as under certain conditions, they may flash upon opening. When opening, point the container away from the face and body and slowly loosen the cap. Although the chances for flash are very remote, never open these containers in a flammable atmosphere. These precautions will also reduce the applicator's exposure to phosphine gas.

Pure phosphine gas is practically insoluble in water, and oils, and is stable at normal 'umigation temperatures. However, it may react with certain metals and cause corrosion, especially at higher temperatures and relative humidities. Metals such as copper, brass, and other copper alloys, and precious metals such as gold and silver are susceptible to corrosion by phosphine. Thus, small electric motors, smoke detectors, brass sprinkler heads, batteries and battery chargers, fork lifts, temperature monitoring devices, computers, calculators, and other electrical equipment should be protected or removed before furnigation.

Phosphine gas will also react with certain metallic saits and, therefore, sensitive items such as photographic film, some inorganic pigments, etc. should not be exposed.

# **DIRECTIONS FOR USE**

This furnigent is a highly hezerdous material and may only be used by individuals trained in its proper use. Before using, read, understand, and follow all precautions and directions on the label and in the INVENTA Corporation Applicator's Manual.

At least two trained persons must be present when the product is applied from within a space to be furnigated or during reentry into a furnigated or partially aerated site.

Prior to applying this product, you must inspect the site to be furnigated to determine if it can be made sufficiently gas tight. You should also develop a plan for monitoring (if not done before), how to most efficiently and safely apply the furnigant, emergency procedures, etc. Notify appropriate company employees and provide relevant safety information to local officials annually for use in the event of an emergency. Follow all local and state regulations. Shiphoids, barges, containers on ships, railroad cars and containers shipped piggyback by rail may be furnigated in transit. However, trucks, vans, trailers, and similar transport vehicles cannot be moved over public roads or highways until furnigation is completed.

Do not furnigate commodities with this product when commodity temperature is below 40°F (5°C).

Please refer to the INVENTA Corporation Applicator's Manual for important information regarding the following:

- DIRECTIONS FOR USE
- AERATION OF FUMIGATED COMMODITIES
- PROTECTIVE CLOTHING
- APPLICATOR AND WORKER EXPOSURE
- PLACARDING OF AREAS

# STORAGE AND DISPOSAL STATEMENTS

#### **GENERAL STORAGE STATEMENTS**

Store in a dry, well ventilated area away from heat, under lock and key. Post as a pesticide storage area. Do not contaminate water, food or feed by storing pesticides in the same areas used to store these commodities. Do not store in buildings where inhabited by humans or domestic animals reside.

#### **GENERAL DISPC SAL STATEMENTS**

Do not contaminate water, food or feed by storage or disposal.

Unreacted or partially reacted aluminum phosphide is acutely hazardous. Improper disposal of excess pesticides, or rinsate is a violation of Federal Law. If these wastes cannot be disposed of by use according to label instructions, contact your State Pesticide or Environmental Control Agency, or jhe jazardous, weste representative at the nearest E.P.A. Regional Office for guidance. For specific instructions, refer to the SPILL AND LEAK PROCEDURES in the INVENTA Corporation Applicator's Manual.

Some local and state waste disposal regulations may vary from the following recommendations. Disposal procedures should be reviewed with appropriate authorities to ensure compliance with local regulations. Contact your state Pesticide or Environmental Control Agency or Hazardous Waste Specialist Afthe nearest E.P.A. Regional Office for guidance.

Triple rinse flasks and stoppers with water. Then offer for recycling or reconditioning, or puncture and dispose of in a sanitary landfill, or by other procedures approved by state and local authorities. Rinsate-may be disposed of in a sanitary sewer, sanitary landfill or by other approved procedures. It is also permissible to remove lids and expose empty flasks outdoors or indoors, in the presence of appropriate mechanical ventilation until residue in the flasks is reacted. Then puncture and dispose of in a sanitary landfill or other approved site, or by other procedures approved by state and local authorities.

If properly exposed, the residual dust remaining after a furnigation with aluminum phosphide will be grayishwhite and contain only a small amount of unreacted material. However, residual dust from incompletely exposed aluminum phosphide will require special care.

Please refer to the INVENTA Corporation Applicator's Manual for Important Information regarding the following:

- DIRECTIONS FOR DISPOSAL OF SPENT RESIDUE FROM ALUMINUM PHOSPHIDE
- . DIRECTIONS FOR DEACTIVATION OF PARTIALLY SPENT RESIDUES FROM ALUMINUM PHOSPHIDE

# SPILL AND LEAK PROCEDURES

A spill, other then incidental to application or normal handling, may produce high levels of gas and, therefore, attending personnel must wear SCBA or its equivalent when the concentration of phosphine gas is unknown. Other N1OSH/MSHA approved respiratory protection may be worn if the concentration is known. Do not use water at any time to clean up a spill of aluminum phosphide. Water in contact with unreacted tablets or pellets will greatly accelerate the production of phosphine gas which could result in a toxic and/or fire hazard. Wear cotton gloves when handling pesticides.

Return all intact aluminum flasks to cardboard cases or other suitable packaging which has been properly marked according to DOT regulations. Notify consignee and shipper of damaged cases.

If aluminum flasks have been punctured or damaged to leak, the container may be temporarily renaired with aluminum tape or the aluminum phosphide may be transferred from the damaged flask to a sound metal container which should be sealed and properly labeled as aluminum phosphide. Transport the damaged containers to an area suitable for pesticide storage for inspection. Further instructions and recommendations may be obtained, if required, from INVENTA Corporation.

If a split has occurred which is only a few minutes old, collect the tablets and pellets and place them back into the original flasks, if they are intact, and stopper tightly. Place the collected tablets and pellets in a sound metal container if the original flasks are damaged. CAUTION: These flasks may flash upon opening at some later time.

If the age of the spill is unknown or if the tablets and pellets have been contaminated with soil, debris, water, etc. gather up the spillage and place it into small open buckets having a capacity no larger than about one gallon. Do not add more than about one flask of spilled material, 1 to 1.5 Kg (2 to 3 lbs), to the bucket. If onsite, wet deactivation is not feasible, these open containers should be transported in open vehicles to a suitable area away from inhabited buildings. Wet deactivation may then be carried out as described under STORAGE AND DISPOSAL Section in the INVENTA Corporation Applicator's Manual.

If the contaminated material is not completely reacted by exposure to atmospheric moisture, deactivate the product by the "Wet Method" as follows:

Deactivating solution is prepared by adding the appropriate amount of low sudsing detergent or surface active agent to water in a drum or other suitable container. A 2% solution or 4 cups in 30 gallons is suggested. The container should be filled with deactivating solution to within a few inches of the top.


The tablets or pellets are poured slowly into the deactivating solution and stirred to thoroughly wet all of the product. This should be done in open air. Aluminum phosphide tablets or pellets should be mixed into no less than about 15 gallons of water-detergent solution for each case of spent material. Allow the mixture to stand, with occasional stirring, for about 36 hours. The resultant slurry will then be safe to dispose of the stand of the safe to dispose of the stand of the safe to dispose of t

Dispose of the slurry of deactivated material, with or without preliminary decanting, at a sanitary tandfill or other suitable site approved by local authorities. Where permissible, this slurry may be poured into a sterm; sewer or out onto the ground.

Respiratory protection is required during wet deactivation of unexposed product. NEVER place peliets, tablets, or dust or other formulations in a closed container such as a dumpster, sealed drum, plastic bag, etc., as flammable concentrations and a flash of phosphine gas are likely to develop.

# STATEMENT OF WARRANTY

Seller warrants that the product conforms to its chemical description and when used according to label directions under normal conditions of use, it is reasonably fit for the purposes stated. Seller makes no other warranty, either express or implied, and buyer assumes all rick should the product be used contrary to label instructions.



# RESTRICTED USE PESTICIDE

# DUE TO ACUTE INHALATION TOXICITY OF HIGHLY TOXIC PHOSPHINE GAS

For retail sale to and use only by Certified Applicators for those uses covered by the applicators certification or persons trained in accordance with the INVENTA Corporation Applicator's Manual working under the direct supervision and in the physical presence of the Certified Applicator. Physical presence means on site or on premises. Read and follow the label and the INVENTA Corporation Applicator's Manual which contains complete instructions for safe use of this pesticide.

# **APPLICATOR'S MANUAL**

for

# **Quik-Fume Tablets, Pellets, and Bags**

# Aluminum Phosphide Furnigant

A fumigant for use against list insects which infest listed raw Agricultural Commodities, Specified Processed Foods, and Animal Feeds

PRECAUCION AL USUARIO: Si usted no lee ingles, no use este producto hasta que la etiqueta se le haya sido explicado amliamente.



# DANGER - PELIGRO - POISON



# PRACTICAL TREATMENT STATEMENT

SYMPTOMS of overexposure to phosphine are headache, dizziness, nausea, difficult breathing, vomiting and diarrhea. In all cases of overexposure, get immediate medical attention. Take the victim to a doctor or emergency treatment facility.

If the gas from aluminum phosphide is INHALED: Move exposed person to fresh air. Keep person warm and make sure person can breathe freely. If breathing has stopped, give artificial respiration by mouth to mouth or other means of resuscitation. Do not give anything by mouth to an unconscious person.

If aluminum phosphide powder, granules, pellets or tablets are SWALLOWED: Drink or administer one or two glasses of water and induce vomitting by touching back of throat with finger, or if available, syrup of ipecac. Do not give anything by mouth if victim is unconscious or not alert.

If powder, granules, or tablets of aluminum phosphide get on SKIN: Brush material off clothes and shoes in a well ventilated area. Allow clothes to aerate in a ventilated area prior to laundering. Wash contaminated bare skin thoroughly with soap and water.

If in EYES: Flush with plenty of water. Get medical attention immediately.

Manufactured by: INVENTA Corporation, Division of United Phosphorus Worll Bombay, INDIA 400 018

Manufactured for: INVENTA Corporation, 14 Phoenix Drive, Mendham, NJ 07945

This manual refers to Quik-F vme Tablets, Pellets, and Bags

E.P.A. Registration Nos. \_\_\_\_\_, and \_\_\_\_, respectively.

IC Revision 880225 Manual



UNDER THE FORM AN EXPENDING 19 CO. AND COMMON SERVICES AND FOR CONTROL OF SHIP SERVICES SUPERIOR TO FIRST CONTROL OF SHIP CONT

THIS PRODUCT IS ACCOMPANIED BY AN APPROVED LABEL AND APPLICATOR'S MANUAL. READ AND UNDERSTAND THE ENTIRE LABELING AND MANUAL. ALL PARTS OF THE LABELING AND MANUAL ARE EQUALLY IMPORTANT FOR SAFE AND EFFECTIVE USE OF THIS PRODUCT. CONTACT


# 14 Phoenix Drive Mendham, NJ 07945 201-543-7239

IF YOU HAVE ANY QUESTIONS REGARDING THIS LABELING OR MANUAL, OR DO NOT UNDERSTAND ANY PART OF THIS LABELING OR MANUAL.

REFER TO THE INVENTA CORPORATION APPLICATOR'S MANUAL FOR DETAILED PRECAUTIONS, RECOMMENDATIONS, AND DIRECTIONS FOR USE.

# STATEMENT OF WARRANTY

Seller warrants that the product conforms to its chemical description and when used according to label directions under normal conditions of use, it is reasonably fit for the purposes stated. Seller makes no other warranty, either express or implied, and buyer assumes all risk should the product be used contrary to label instructions.



# **TABLE OF CONTENTS**

# 1. INTRODUCTION AND SAFETY RECOMMENDATION SUMMARY

#### 2. PRECAUTIONARY STATEMENTS

- A. Hazards to Humans and Domestic Animals
- **B. Practical Treatment Statement**
- C. Note to Physician
- D. Physical and Chemical Hazards

# 3. DIRECTIONS FOR USE

- A. General
- **B.** Efficacy
- C. Exposure Conditions
- D. Commodities Which May Be Furnigated with Quilt Furne
- E. Recommended Dosages
- F. Application Procedures

# 4. AERATION OF FUMIGATED COMMODITIES

- A. Foods and Feeds
- B. Tobacco

# 5. PLACARDING OF FUMIGATED AREAS

- 6. PROTECTIVE CLOTHING
- 7. APPLICATOR AND WORKER EXPOSURE
- 8. STORAGE INSTRUCTIONS

# 9.DISPOSAL INSTRUCTIONS

- A. General Disposal Statements
- B. Directions Disposal Of Residual Dust From Quik-Furne
- C. Directions For Deactivation Of Residual Dust From Quik-Fume

### 10.SPILL AND LEAK PROCEDURES

# **SECTION 1**

# INTRODUCTION

Quik-Furne furnigants are used to protect stored commodities from damage by insects and for control of burrowing pests. Furnigation of stored products with Quik-Furne in the manner prescribed in the labeling does not contaminate the stored commodity. Quik-Furne and other Aluminum Phosphide furnigants are acted upon by atmospheric moisture to produce phosphine (PH<sub>3</sub>, hydrogen phosphide) gas. Quik-Furne tablets, peliets, and bags contain aluminum phosphide (AIP) as their active ingredient and will liberate phosphine via the following chemical reaction:

$$AIP + 3H_2O - > AI(OH)_3 + PH_3$$

Phosphine gas is highly toxic to insect, burrowing pests, humans and other forms of animal life. In addition to its toxic properties, the gas will corrode certain metals and may ignite spontaneously in air at concentrations above its lower flammable limit of 1.8% (v/v). These hazards will be described in greater detail later on in this Manual for Quik-Fume pellets, tablets, and bags. Quik-Fume also contains ammonium carbamate which liberates ammonia and carbon dioxide as follows:

These gases are essentially nonflammable and act as inerting agents to reduce fire hazards. The ammonia gas also serves as a warning agent.

Quik-Fume is prepared in three forms, tablets, pellets, and bags. The rounded tablets with approximately 3 grams and release 1 gram of phosphine gas. They are about 10mm in diameter and are bulk packaged in resealable aluminum flasks containing 100 or 500 tablets each. The pellets weigh approximately 0.6 gram and release 0.2 gram of phosphine gas. They are about 10mm in diameter and are packaged in resealable flasks containing about 1660 pellets. The bags weigh 34 grams each and release 11 grams of phosphine gas. They are packaged in aluminum containers of six, ten, or one hundred bags to the container. The bags are packaged in an oxygen free environment.

Upon exposure to air Quik-Fume pellets, tablets, and bags begin to react with atmospheric moisture to produce small quantities of phosphine gas. This reaction starts slowly, gradually accelerates and then tapers off again as the aluminum phosphide is spent. Quik-Fume pellets react somewhat faster than do the tablets and bags. The rates of decomposition of the tablets, pellets and bags will vary depending upon moisture and temperature conditions. For example, when moisture and temperature of the fumigated commodity are high, decomposition of Quik-Fume may be complete in less than 3 days. However at lower ambient temperatures and relative humidity levels, decomposition of Quik-Fume may require 5 days or more. After decomposition, Quik-Fume leaves a gray-white powder composed almost entirely of aluminum hydroxide and other approved inert ingredients. If properly exposed, the spent Quik-Fume will normally contain only a small amount of unreacted aluminum phosphide and may be disposed without hazard. While not considered a hazardous waste, partially spent residual from incompletely exposed Quik-Fume will require special care. Precautions and instructions for further deactivation and disposal will be given later in the INVENTA Corporation Applicator's Manual.

Quik-Furne pellets, tablets and bags are supplied in gas tight containers and their shelf life in unlimited as long as the packaging remains intact. Once opened for furnigation, the flasks of tablets and pellets may be tightly resealed and stored for future use. The Quik-Furne bags container cannot be resealed for future use. Storage and handling instructions will be given in detail later in the INVENTA Corporation Applicator's Manual.

#### SAFETY RECOMMENDATION SUMMARY

- 1. Carefully read the labeling and follow instructions.
- 2. Never furnigate alone from inside the storage structure.
- 3. Person supervising must be a certified furnigator and the personnel assisting must be trained in the use of aluminium phosphide. Never allow uninstructed personnel to handle aluminum phosphide.
- 4. Approved respiratory protection must be available for the furnigation of structures from within.
- 5. Wear dry gloves of cotton or other materials if contact with Quik-Fume tablets, pellets or bags is likely. Aerate used gloves and other contaminated clothing in a well ventilated area prior to laundering. Wash hands thoroughly after using Quik-Fume.

- 6. Open furnicent containers in open air only. Never open in a flammable atmosphere.
- 7. Do not allow Quik-Furne to contact water, or pile up.
- 8. Dispose of empty containers and spent residual dust in a manner consistent with the label instructions.
- 9. Post warning placards on fumigated areas.
- 10. Prior to furnigation, notify appropriate company employees. Provide to local officials (fire department, rescue squad, police, etc.) on an annual basis relevant safety information for use in the event of an emergency.
- 11. Phosphine furnigants are not to be used for vacuum furnigations.
- 12. Exposure to phosphine must not exceed the eight hour TWA of 0.3 ppm during application, or a ceiling concentration of 0.3 ppm after application is completed.
- 13. Furnigated areas must be aerated to 0.3 ppm phosphine or less prior to reentry by unprotected workers.
- 14. Finished foods and feeds that have been furnigated with Quik-Furne must be aerated for 48 hours prior to offering to the end use consumer.
- 15. Transfer of a treated commodity to another site without complete aeration is permissible provided that the new storage site is placarded if the phosphine concentration is above 0.3 ppm.
- 16. Keep containers of Quik-Fume tightly closed except while removing product for application.
- 17. Protect materials containing metals such as copper, silver, gold and their alloys and salts from corrosive exposure to phosphine.
- 18. Tablets, pellets and bags must not come in contact with any processed food, except, that tablets and pellets may be added directly to processed brewers rice, malt and corn grits used in the manufacture of beer.
- 19. Do not use aluminum phosphide containers for any purpose other than recycling or reconditioning.
- 20. OSHA recommends preexposure screening of employees to detect impaired pulmonary function. They recommend that any employees developing this condition be referred for medical examination.

# **SECTION 2**

# PRECAUTIONARY STATEMENTS

#### A. HAZARDS TO HUMANS AND DOMESTIC ANIMALS

DANGER: Aluminum phosphide powder, granules or tablets may be fatal if swallowed. Do not get in eyes, on skin or on clothing. Do not eat, drink or smoke while handling aluminum phosphide fumigants. If a sealed container is opened, or if the material comes into contact with moisture, water or acids, extremely toxic phosphine gas will be released. If a garlic odor is detected, refer to on APPLICATOR AND WORKER EXPOSURE Section of the INVENTA Corporation Applicator's Manual for appropriate monitoring procedures. Pure phosphine gas is odorless; the odor is due to a contaminant. Since an odor may not be detected under certain circumstances, the absence of a garlic odor does not mean that phosphine gas is absent. Observe proper application, aeration, reentry and disposal procedures specified elsewhere in the labeling and in this manual to prevent overexposure.

# **B. PRACTICAL TREATMENT STATEMENT**

SYMPTOMS of overexposure to phosphine are headache, dizziness, nausea, difficult breathing, vomiting and diarrhea. In all cases of overexposure, get immediate medical attention. Take the victim to a doctor or emergency treatment facility.

If the gas from aluminum phosphide is INHALED: Move exposed person to fresh air. Keep person warm and make sure person can breathe freely. If breathing has stopped, give artificial respiration by mouth to mouth or other means of resuscitation. Do not give anything by mouth to an unconscious person.

It aluminum phosphide powder, granules, pellets or tablets are SWALLOWED: Drink or administer one or two glasses of water and induce vomiting by touching back of throat with finger, or if available, syrup of ipecac. Do not give anything by mouth if victim is unconscious or not alert.

If powder, granules, or tablets of aluminum phosphide get on SKIN: Brush material off clothes and shoes in a well ventilated area. Allow clothes to aerate in a ventilated area prior to laundering. Wash contaminated bare skin thoroughly with soap and water.

If in EYES: Flush with plenty of water. Get medical attention immediately.

# C. NOTE TO PHYSICIAN (We recommend that this Section be given to the attending physician):

Aluminum phosphide granules, powder, or tablets react with moisture in the air, acids, and many other liquids to release phosphine gas. Mild exposure by inhalation causes malaise, ringing of ears, fatigue, nausea, ar. 1 pressure in the chest which is relieved by removal to fresh air.

Moderate poisoning causes weakness, vomiting, epigastric pain, chest pain, diarrhea and dyspnea.

Severe poisoning may occur in a few hours to several days, resulting in pulmonary edema and may lead to dizziness, cyanosis, unconsciousness, and death.

In sufficient quantity, phosphine affects the liver, kidneys, lungs, nervous system and circulatory system. Inhalation can cause lung edema and hyperemia, small perivascular brain hemorrhages, and brain edema. Ingestion can cause lung and brain symptoms, but damage to the viscera is more common. Phosphine poisoning may result in (1) pulmonary edema; (2) liver elevated serum GOT, LDH and alkaline phosphatase, reduced prothrombin, hemorrhage and jaundice; and (3) kidney hematuria and anuria. Pathology is characteristic of hypoxia. Frequent exposure over a period of days or weeks may cause poisoning. Treatment is symptomatic. For further information, contact the nearest National Poison Control Center.

#### D. PHYSICAL AND CHEMICAL HAZARDS

Aluminum phosphide in tablets, pellets, and partially spent dust will release phosphine gas if exposed to moisture from the air or if it comes into contact with water, acids and many other liquids. Piling of tablets, pellets, or dust from their fragmentation may cause a temperature increase and confine the release of gas so that ignition could occur.

Always open containers of aluminum phosphide products outdoors or indoors, in the presence of appropriate mechanical ventilation as under certain conditions, they may flash upon opening. When opening, point the container away from the face and body and slowly loosen the cap. Although the chances for flash are very remote, never open the containers in a flammable atmosphere. <u>Thuse precautions will also reduce the applicator's exposure to phosphine das.</u>

Pure phosphine gas is practically insoluble in water, and oils, and is stable at normal furnigation temperatures. However, it may react with certain metals and cause corrosion, especially at higher temperatures and relative humidities. Metals such as copper, brass, and other copper alloys, and precious metals such as gold and silver are susceptible to corrosion by phosphine. Thus, small electric motors, smoke detectors, brass sprinkler heads, batteries and battery chargers, fork lifts, temperature monitoring systems, switching gears, communication devices, computers, calculators, and other electrical equipment should be protected or removed before furnigation.

Phosphine gas will also react with certain metallic salts and, therefore, sensitive items such as photographic film, some inorganic pigments, etc. should not be exposed.

# Section 3 DIRECTIONS FOR USE

### A. GENERAL

It is a violation of Federal Law to use this product in a manner inconsistent with its labeling.

- 1. Quik-Furne tablets, pellets and bags are RESTRICTED USE PESTICIDE due to the acute inhalation of phosphine gas. These products are for retail sale to and use only by certified applicators for uses covered by the applicators certification or person trained in accordance with the manual, working under the direct supervision and in the physical presence of the applicator. Physical presence means on site or on the premises. Read and follow the label and the manual which contains complete instructions for the safe use of this pesticide.
- 2. Quik-Fume is a highly hazardous material and should be used only by individuals trained in its proper use. Before using read and follow the precautions and directions contained in the Quik-Fume label and in the IN-VENTA Corporation Application Manual.

Persons working with Quik-Fume should be knowledgeable of the hazards of this chemical and trained in the use of required respiratory equipment and detector device, emergency procedures and use of the fumigant.

Additional copies of the INVENTA Corporation Applicator's Manual are available from:

INVENTA Corporation 14 Phoenix Drive Mendham, NJ 07945 201-543-7239

- 3. At least two persons trained in the use of aluminum phosphide must be present during fumigation of structure if entry into the structure is required for application of the fumigant. Two trained persons must also be present during reentry into fumigated or partially aerated structures. Only one trained person is required to be present when Quik-Fume is applied from outside the area to be treated.
- 4. Ship holds, barges, containers on ships, railroad cars and containers shipped piggyback by railway may be fumigated intransit. However, trucks, vans, trailers and similar transport vehicles cannot be moved over public roads and highways until they are aerated and the warning placards removed.
- 5. Do not fumigate commodities with Quik-Fume when commodity temperature is below 40° F (5° C).
- 6. The site to be furnigated must first be inspected to determine if it can be made sufficiently gas tight. There a plan should be developed to provide for safe and efficient application of the furnigant to include emergency procedures etc., where required, and to decide how monitoring should be conducted to prevent excessive exposures.
- 7. Wear dry gloves of cotton or other material while handling Quik-Fume tablets, pellets, or bags. Wash hands thoroughly after use
- 8. Phosphine gas may flash at concentrations above its flammable limit. Therefore, always open Quik-Fume contains in open air and never in a flammable atmosphere. This precaution will not only prevent harm in the unlikely event of a flash but, will reduce the applicators exposure to phosphine gas.
- 9. Piling of tablets, pellets or bags or addition of water to Guik-Furne may speed up the reaction, cause a temperature increase and confine the gas so that ignition could occur.
- 10. As much as is possible protect unused Quik-Furne from excessive exposure to atmospheric moisture during application and tightly reseal the aluminum lask prior to returning tablets or pellets to storage. Quik-Furne bag containers once opened cannot be resealed for future use.
- 11. Phosphine gas may react with certain metals and their salts to produce corrosion. Copper, copper alloys and precious metals such as sliver and gold are susceptible to corrosion and items containing these elements should be removed or protected prior to fumigation with Quik-Fume.
- 12. Do not allow Quik-Fume or its residual dust to come in contact with processed foods or commodity packages intended for retailers except that Quik-Fume tablets, pellets or bags may be added directly to processed brewers rice, malt and corn grits used in the manufacture of beer.
- 13. Respiratory protection approved for the concentration to which the furnigator will be exposed must be available if Quik-Furne is to be applied from within the structure to be furnigated. Respiratory protection need

not be available for uses such as outdoor application, addition of tablets or pallets to automatic dispensing devices, etc., if exposures above the TLV's will not be encountered. A NIOSH/MSHA approved, full-face gas mask phosphine canister combination may be used at levels up to 15 ppm. Above this level or in situations where the phosphine concentration is unknown a NIOSH/MSHA approved, self-contained breathing apparatus (SCBA) or its equivalent must be used.

14. Notify appropriate company employees prior to furnigation. Provide to local officials (fire department, rescue squad, police, etc.) on annual basis relevant safety information for use in the event of an emergency.

#### **B. EFFICACY**

Quik-Furne has been found effective against the following insects and their preadult stages ( eggs, larvae, and pupee):

- almond moth
  angoumois grain moth
  bean weevil
  bees
  cadelle
  cereal leaf beetle
  cigarette beetle
  confused flour beetle
  dermestid beetle
  dried fruit beetle
  dried fruit moth
- European grain moth
  flat grain beetle
  fruit flies
  granary weevil
  greater wax moth
  hairy fungus beetle
  Hessian fly
  Indian meal moth
  Khapra beetle
  lesser grain borer
  maize weevil
- Meditarranean flour moth
  pi ': boliworm
  raisin moth
  red flour beetle
  rice weevil
  rusty grain weevil
  saw-toothed grain beetle
  spider beetles
  tobacco moth
  vellow meal worm

Although it is possible to achieve total control of the listed insect pests, this is frequently not realized in actual practice. Factors contributing to less than 100% control are leaks, poor gas distribution, unfavorable exposure conditions, etc. In addition, some insects are less susceptible to phosphine than others. If maximum control is to be attained extreme care must be taken in sealing, the higher dosages must be used, exposure periods must be lengthened, proper application procedures followed and temperature and humidity must be favorable.

#### C. EXPOSURE CONDITIONS

The following conditions may be used as a guide in determining the minimum length of the exposure period at the indicated temperatures:

# Minimum Exposure Periods for Quik-Fume

Temperature	Peliets	Tablets	Bags
below 40°F (5°C)	Do not fumigate	Do not furnigate	Do not fumigate
40°-53°F (5-12°C)	8 days (192 hours)	10 days (240 hours)	14 days (336 hours)
54°-59°F (12-15°C)	4 days (96 hours)	5 days (120 hours)	7 days (168 hours)
60°-68°F (16-20°C)	3 days (72 hours)	4 days (96 hours)	4 days (96 hours)
above 68°F (20°C)	2 days (48 hours)	3 days (72 hours)	3 days (72 hours)

The length of the furnigation must be great enough to provide for adequate control of the insect pests which infest the commodity being treated. Additionally, the furnigation period should be long enough to allow for more or less complete reaction of Quik-Furne with moisture so that little or no unreacted aluminum phosphide remains. This will minimize exposures during further storage and/or processing of the treated bulk commodity as well as reduce hazards in the disposal of partially spent aluminum phosphide products remaining after space furnigations. The proper length of the furnigation period will vary with exposure conditions since, in general, insects are more difficult to control at lower temperatures and the rate of phosphine gas production by Quik-Furne is less at lower temperatures and humidities.

it should be noted that there is little to be gained by extending the exposure period if the structure to be furnigated has not been carefully sealed or if the distribution of gas is poor and insects are not subjected to lethal concentrations of phosphine. Careful sealing is required to ensure that adequate gas levels are retained and proper application procedures must be followed to provide satisfactory distribution of phosphine gas. Some structures can only be treated when completely tarped, while others cannot be properly sealed by any means and should not be furnigated. Exposure times must be lengthened to allow for penetration of gas throughout the commodity when furnigant is not uniformly added to the mass, for example, by surface application or shallow probing. This is particularly important in the furnigation of a bulk commodity contained in large storages.

Remember, exposure periods in the table are minimum periods and may not be adequate to control all stored product pests under all conditions nor will they always provide for total reaction of Quik-Fume, particularly if temperatures and commodity moisture levels or humidity are low during the fumigation.

# D. COMMODITIES WHICH MAY BE FUMIGATED WITH Quik-Fume

Quik-Furne may be used for the furnigation of the listed raw agricultural commodities, animal feed and feed ingredients, processed foods, tobacco and certain other nonfood items.

# 1. Raw Agricultural Commodities, Animal Feed and Feed Ingredients

Quik-Furne tablets, pellets and bags may be added directly to animal feed, feed ingredients and raw agricultural commodities stored in bulk. For these commodities not stored in bulk, Quik-Furne may be placed in moisture permeable envelopes, on trays, in bags, etc. and furnigated as with processed foods.

# Raw Agricultural Commodities and Animal Feed and Feed Ingredients

# Which May Be Furnigated With Quik-Furne

- Almonds
  Animal Feed
- Vegetables
- Millet
- SoybeansSunflower Seeds
- Tricale
- Vegetable Seeds
- Walnuts

- Wheat
- Filberts
- Flower Seed
- Grass Seed
- Sorghum
- Brazil Nuts
- Cashews
- Cocoa Beans
- Coffee Beans

- Corn
- Cottonseed
- Dates
- Safflower Seed
- Sesame Seed
- Seed & Pod Vegetables
- Barley
- Oats

- Peanuts
- ∂ecans
- Pistachio Nuts
- Popcom
- Rice Rve

#### 2. Processed Foods

The listed processed foods may be furnigated with Quik-Furne. Under 1:0 conditions shall any processed food or bagged commodity come in contact with Quik-Furne tablets, pellets, bags, or residual dust except that Quik-Furne may be added directly to processed brewer's rice, malt and corn grits for use in the manufacturer of beer.

- Processed candy and sugar
- Cereal flours and bakery mixes
- Cereal foods (including cookies, crackers, macarchi, noodles, pasta, pretzels, snack foods and spaghetti)
- Processed cereals (including milled fractions and packaged cereals)
- Cheese and cheese byproducts
- Chocolate and chocolate products (assorted chocolate, chocolate liquor, cocoa, cocoa powder, dark chocolate coating and milk chocolate)
- Processed coffee
- Corn grits
- · Cured, dried and processed meat products and dried fish
- Dates and figs
- Dried eggs and egg yolk solids
- Dried milk, dried powdered milk, nondairy creamers, and nonfat dried milk
- Dried or dehydrated fruits (apples, dates, figs, peaches, pears, prunes, raisins and sultanas)

- Processed herbs, spices, seasonings and condiments
- \_ Mali
- Processed nuts (almonds, apricot kernels, Brazil nuts, cashews, filberts, peanuts, pecans, pistachio nuts, and walnuts)
- Processed cats (including oatmeal)
- Rice (brewers rice, grits, enriched and polished wild rice)
- Processed tea
- Dried and dehydrated vegetables (beans, carrots, lentils, peas, potato products and spinach)
- Yeast (including primary yeast)
- 3. Nonfood Commodities, Including Tobacco

The listed nonfood items may be furnigated with Quik-Furne. Tobacco and certain other of the nonfood commodities should not be contacted by tablets, pellets or residual dust.

- Processed or unprocessed cotton, wool and other natural fibers or cloth,
- Clothing
- Straw and hay
- Feathers
- Human hair, rubberized hair, vulcanized hair, and mohair
- Leather products, animal hides and furs
- Tobacco
- Wood, cut trees, wood chips and wood and bamboo products
- Paper and paper products
- Dried plants and flowers
- Seeds (grass seed, ornamental herbaceous plant seed and vegetable seed)

#### E. RECOMMENDED DOSAGES

Phosphine is a mobile gas and will penetrate to all parts of the storage structure. Therefore, dosage must be based upon the total volume of the space being treated and not on the amount of commodity it contains. The same amount of Quik-Fume is required to treat a 30,000 bushel silo whether it is empty or full of grain unless, the surface of the commodity is sealed off by a tarpaulin. The following dosage ranges are recommended for bulk and space fumigations:

# Dosage Guidelines For Fumigation With Quik-Fume

Product	per 1000 cu ft.*	per 1000 bu.*
Bags	2-6	2-6
Pellets	100-725	120-900
Tablets	20-145	25-180

<sup>\*</sup> Dosage range for dates, nuts and dried fruits is 100-200 pellets, 20-40 tablets, 2-6 bags/1000 cu. ft; 125-250 pellets, 25-50 tablets, 2-6 bags/1000 bu.

These dosages are not to be exceeded. It is important to be aware that a shortened exposure period cannot be fully compensated for with an increased dosage of phosphine. The wide range of dosages listed above is required to handle the variety of furnigation situations encountered in practice. Some what higher dosages are usually recommended under cooler, drier conditions or where exposure periods are relatively short. However, the major factor in selection of dosage is the ability of the structure to hold phosphine gas during the furnigation. A good illustration of this point is comparison of the low dosages required to treat modern, well-sealed warehouses with the higher range used for poorly constructed buildings that cannot be sealed adequately. In certain other furnigations, proper distribution of lethal concentrations of gas to reach all parts of the structure becomes a very important factor in dose selection. An example where this may occur is in the treatment of grain stored in tall silos. Poor gas distribution frequently results when the furnigant cannot be uniformly added to the grain and it must be treated by surface application. Although it is permissible to

choose from the full range of dosages listed above, the following dosages are recommended for the various types of furnigations:

# Recommended Quik-Fume Dosages For Various Types of Fumigations

Type of Fumigation	Bags	Pellets	Tablets
1. Space	_		
Mills , warehouse etc.	2-6/1000 cu. ft.	100-300/1000 cu. ft.	20-80/1000 cu. ft.
Bagged commodities	2-6/1000 cu. ft.	150-300/1000 cu. ft.	30-60/1000 cu. ft.
Processed fruits & nuts	2-6/1000 cu. ft.	100-200/1000 cu. ft.	20-40/1000 cu. ft.
Stored tobacco	2-6/1000 cu. ft.	100-200/1000 cu, ft.	20-40/1000 cu. ft.
2. Bulk Stored Commodities			
Vertical storages	2-6/1000 cu. ft.	150-300/1000 cu. ft.	30-60/1000 cu. ft.
	2-6/1000 cu. ft.	200-375/1000 cu. ft.	40-75/1000 cu. ft.
Tanks	2-6/1000 cu. ft.	150-350/1000 cu. ft.	30-70/1000 cu. ft.
	2-6/1000 cu. ft.	200-450/1000 cu. ft.	40-90/1000 cu. ft.
Flat storages	2-6/1000 cu. ft.	250-725/1000 cu. ft.	50-145/1000 cu. ft.
-	2-6/1000 cu. ft.	300-900/1000 cu. ft.	60-180/1000 cu. ft.
Farm bins	2-6/1000 cu. ft.	350-725/1000 cu. ft.	70-145/1000 cu. ft.
	2-6/1000 cu. ft.	450-900/1000 cu. ft.	90-180/1000 cu. ft.
Bunker & tarped ground storages	2-6/1000 cu. ft.	150-400/1000 cu. ft.	30-80/1000 cu. ft.
storages	2-6/1000 cu. ft.	200-500/1000 cu. ft.	40-100/1000 cu. ft.
Dallage	2-6/1000 cu. ft.	150-325/1000 cu. ft.	30-65/1000 cu. ft.
Railcars	2-6/1000 cu. ft.	200-400/1000 cu. ft.	40-80/1000 cu. ft.
<b>D</b>	2-6/1000 cu. ft.	150-400/1000 cu. ft.	30-80/1000 cu. ft.
Barges	2-6/1000 cu. ft.	200-500/1000 cu. ft.	40-100/1000 cu. ft.
		200 000, 1000 00. 11.	TO TOO TOO QUE IL.
Shipholds	2-6/1000 cu. ft.	150-330/1000 cu. ft.	30-66/1000 cu. ft.
Sirpious	2-6/1000 cu. ft.	200-375/1000 cu. ft.	40-75/1000 cu. ft.
	• • •		<del></del>

Higher dosages are recommended in structures that are loose construction and in the fumigation of bulk stored commodities in which diffusion will be slowed and result in poor distribution of phosphine gas.

#### F. APPLICATION PROCEDURES

#### 1. General Statement

Regardless of the type of storage to be treated, there are several important factors common to all application procedures. A number of these points have been covered in other sections of the INVENTA Corporation Applicator's Manual but are listed again in the following for completeness.

- a. A plan should be devised for application, aeration and disposal of the furnigant to keep at a minimum any exposures to phosphine. See the requirements in the APPLICATOR AND WORKER EXPOSURE Section of the INVENTA Corporation Applicator's Manual.
- b. Quik-Fume tablets or pellets should be applied to provide effective gas concentrations throughout the storage. When tablets or pellets are not applied uniformly to a bulk commodity (surface application in a tall silo or shipshold for example), exposure times should be lengthened to allow for penetration of gas throughout the storage.
- c. The storage structure should be sealed to maintain a suitable gas concentration over the time period required for control of insect pests.
- d. Ideally, exposure periods should be long enough to provide for adequate control of insect pests and also more or less completely react the furnigant.

- e. Piling of large numbers of tablets or pellets, whether applied to a bulk commodity or for space fumigation, may prevent complete breakdown of the product by limiting its access to moist air. This can result in decreased efficacy as a result of poor gas release and may leave an active residual for disposal which contains considerable amounts of unreacted aluminum phosphide. Piling of product may also result in increased hazard of fire if water should come into contact with the mass of aluminum phosphide.
- f. Contact with water should be carefully avoided when applying Quik-Furne for treatment of bulk commodities or space.
- g. Aluminum phosphide furnigants should not be applied to confined spaces where the concentration of phosphine may build up to exceed its lower flammable limit.
- h. Observe the precautionary and safety statements mentioned in the INVENTA Corporation Applicator's Manual.

NOTE: The following instructions are intended to provide general guidelines for typical furnigations. These instructions are not intended to cover every type of situation nor are they meant to be restrictive. Other procedures may be used if they are safe, effective and consistent with the properties of aluminum phosphide products.

# 2. Fumigations of Farm Bins

Leakage is the single most important cause of failures in the treatment of farm storages. Since these storages are often small, they usually have a higher leakage area in proportion to their capacity. Most wooden storage structures are so porous that they cannot be successfully furnigated unless they are completely tarped. Do not furnigate storages which will be entered by humans or animals prior to aeration. Do not furnigate areas which house sensitive equipment containing copper or other metals likely to be corroded by phosphine gas. (See Physical and Chemical Hazards Section in the Iventa Corporation Applicator's Manual.)

Seal the bin as tightly as possible. It is recommended that the surface of the grain be covered with a tarpaulin after Quik-Fume has been applied. Tarping the grain surface will greatly reduce the leak rate of the gas as well as reduce the amount of Quik-Fume required. Only the volume below the tarp must be dosed. If not tarped, the entire volume of the storage must be treated, whether full or empty.

Quik-Furne tablets, pellets, or bags may be scattered over the surface or probed into the grain using a rigid PVC pipe about 5 to 7 feet in length and having a diameter of 1 1/4 inches. Immediately cover the surface of the grain with a plastic tarpaulin. Place no more than 25 percent of the total dose at the bottom if the bin is equipped with aeration fans. CAUTION: Make sure that the aeration duct is dry before adding Quik-Furne. Addition of Quik-Furne to water in an aeration duct may result in a fire. Seal the aeration fan with 4 mil plastic sheeting.

Post furnigation warning signs on entrances to the bin and near the ladder.

Following aeration of the bin, the surface of the grain may be sprayed with an approved protectant to discourage reinfestation.

# 3. Fumigation of Flat Storages

- a. Establish a plan for application of furnigant to the structure. Treatment of these types of storages may require considerable effort, therefore, sufficient manpower should be available to complete the work rapidly enough to prevent excessive exposure to phosphine gas. Vent flasks outside the storage, conduct furnigations during the cooler periods and employ other work practices to minimize exposures. It is often advisable to wear respiratory protection during application of furnigant to flat storages. Refer to the sections on APPLICATOR AND WORKER EXPOSURE AND RESPIRATORY PROTECTION in the INVENTA Corporation Applicator's Manual.
- b. Seal any vents, cracks and other sources of leaks.
- c. Apply tablets, pellets, or bags by surface application, shallow probing, deep probing or uniform addition as the bin is filled.

Storages requiring more than 24 hours to fill should not be treated by addition of furnigant to the commodity stream as large quantities of phosphine may escape before the bin is completely sealed. Probes should be inserted vertically at intervals along the length and width of the flat storage. Pellets, tablets or bags may be dropped in a the probe authervals as it is withdrawn.

Surface application may be used if the bic can be sufficiently gas tight to contain the furnigant gas long enough for it to penetrate the constructive at this instance, it is advisable to place about 25 percent of the

dosages in the floor level aeration ducts. Check the ducts prior to addition of Quik-Furne to make sure that they contain no water.

- d. Tarping the surface of the commodity is often advisable, particularly if the overhead of the storage cannot be well sealed.
- e. Lock all entrances to the storage and post fumigation warning placards.
- 4. Furnigation of Vertical Storages (Concrete Upright Bins And Other Silos In Which Grain Can Be Rapidly Transferred)
  - a. Close all openings and seal all cracks to make the structure as airtight as possible. Prior to the furnigation, seal the vents near the bin top which connects to adjacent bins.
  - b. Pellets, or tablets may be applied continuously by hand or by an automatic dispenser on the head-house/gallery belt or the fill opening as the commodity is loaded into the bin. An automatic dispenser may also be used to add Quik-Fume into the commodity stream in the leg of the elevator.
  - c. Seal the bin deck openings after the fumigation has been completed.
  - d. Bins requiring more than 24 hours to fill should not be furnigated by continuous addition into the commodity stream. These bins must be furnigated by probing surface application, or other appropriate means. Exposure periods should be lengthened to allow for diffusion of gas to all parts of the bins if Quik-Furne has not been applied uniformly throughout the commodity mass.
  - e. Place warning placards on the discharge gate and on all entrances.

# 5. Furnigation of Mills, Food Processing Plants and Warehouses

- a. Using the label, calculate the length of the fumigation and dosage of tablets, pellets or bags to be applied based upon volume of the building, air and/or commodity temperature and the general tightness of the structure.
- b. Carefully seal and placard the space to be furnigated.
- c. Place trays or sheets of Kraft paper or foil, up to 12 sq.ft. (1.1 sq. M) in area, on the floor throughout the structure to hold Quik-Fume pellets or tablets. Bags should be spread evenly on the floor. Use total floor space.
- d. Spread Quik-Fume on the sheets at a density no greater than 30 tablets per sq. ft. This corresponds slightly more than one-half flask of tablets of one-half flask of pellets per 3'x 4" sheet. Check to see that Quik-Fume has not piled up and that it is spread evenly to minimize contact between the individual pellets, tablets, and bags.
- e. Doors leading to the fumigated space should be closed, sealed, locked, and placarded with warning signs.
- f. The fumigation period usually lasts from 2 to 5 days, depending upon the temperature. Upon completion of the exposure period, windows, doors, vents, etc. should be opened and the fumigated structure allowed to aerate for at least two hours before entering. When required, gas concentration readings may be taken using low level detector tubes or similar devices to ensure safety of personnel who reenter the treated area. Refer to the Section on APPLICATOR AND WORKER EXPOSURE Section in the INVENTA Corporation Applicator's Manual.
- g. Collect the spent bags, and Quik-Fume dust and dispose of it, with or without further deactivation, following the recommendations given under DISPOSAL INSTRUCTIONS in the INVENTA Corporation Applicator's Manual.
- h. Remove fumigation warning placards from the aerated structure.

# 6. Fumigation of Railcars, Containers, Trucks, Vans and Other Transport Vehicles

Railcars, containers, trucks, vans and other transport vehicles loaded with bulk commodities to which Quik-Fume tablets, pellets, or bags may be added directly are treated in essentially the same way as any other flat storage facility. Quik-Fume may be added as the vehicle is being filled, the dose may be scattered over the surface after loading has been completed or the tablets, pellets, or bags may be probed below the surface, carefully seal any vents, cracks, or other leaks. Remember, railcars and containers shipped piggyback by rail may be furnigated intransit, but it is not legal to move trucks, trailers, vans, etc. over public roads or highways until they are aerated. See PLACARDING OF FUM:GATED AREAS in the INVENTA Corporation Applicator's Manual. Notify the consignee if the commodity is to be shipped under furnigation with Quik-Fume. If the consignee is unfamiliar with proper handling of treated railcars, it is recommended that they be provided with the necessary information.

# 7. Tarpaulin and Bunker Fumigations

Use of plastic sheeting or tarpaulins to cover commodities is one of the easiest means for providing relatively gas tight enclosures which are very will suited for furnigation. Polyethylene tarps are penetrated only very slowly by phosphine gas, and tight coverings are readily formed from the sheets. The volume of these enclosures may vary widely from a few cubic feet, for example, a furnigation tarpaulin placed over a small stack of a bagged commodity, to a plastic bunker storage capable of holding 600,000 bushels of grain or more.

An enclosure suitable for fumigation may be formed by covering bulk or packaged commodity with polyethylene sheeting. The sheets may be taped together to provide a sufficient width of material to ensure that adequate sealing is obtained. If the flooring upon which the commodity rests is of wood or other porous material, it should be repositioned onto tarpaulin prior to covering for fumigation. The plastic covering of the pile may be sealed to the floor using sand or water snakes, by shoveling soil or sand onto the ends of the plastic covering or by other suitable procedures. The poly covering should be reinforced by tape or other means around any sharp corners or edges in the stack to reduce the risk of tearing. Thinner polyethylene sheeting, about 2 mil. is suitable for most indoor tarp fumigations and for sealing of windows, doors and other openings in structures. However, 4 mil poly or thicker is more suitable for outdoor applications where wind or other mechanical stresses are likely to be encountered.

Tablets, pellets or bags may be applied to the tarped stack or bunker storage of bulk commodity through slits in the polyethylene covering. Probing or other means of dosing may be used. Avoid application of large amounts of Quik-Furne at any one point. The Quik-Furne should be added below the surface of the commodity if condensation or other source of moisture is likely to form beneath the poly. The slits in the covering should be carefully taped to prevent loss of gas once the dose has been applied. Quik-Furne bags are recommended for the treatment of bagged commodities and processed foods although tablets and pellets on trays or sheets of Kraft paper may be used. Care should be taken to see that the polyethylene sheeting is not allowed to cover the Quik-Furne and prevent contact with moist air or confine the gas.

Distribution of phosphine ga. is generally not a problem in the treatment of bagged commodities and processed foods. However, furnigation of larger bunker storages containing bulk commodity will require proper application procedures to obtain adequate results.

Place warning placards at conspicuous locations on the enclosure.

#### 8. Fumigation of Ships

#### a. General Information

IMPORTANT- shipboard, intransit ship or ship holds furnigation is also governed by U.S. Coast Guard Regulation 46 CFR 147A. Refer to this regulation prior to furnigation.

## b. Pre-Voyage Fumigation Procedures

- 1. Prior to fumigating a vessel for intransit cargo fumigation, the master of the vessel, or his representative, and the fumigator must determine whether the vessel is suitably designed and configured to allow for safe occupancy by the ships crew throughout the duration of the fumigation. If it is determined that the design and configuration of the vessel does not allow safe occupancy by the ships crew throughout the duration of the fumigation, then the vessel will not be fumigated unless all crew members are removed from the vessel. The crew members will not be allowed to reoccupy the vessel until the vessel has been properly aerated and a determination has been made by the master of the vessel and the fumigator that the vessel is safe for occupancy.
- 2. The person responsible for the furnigation must notify the master of the vessel, or his representative, of the requirements relating to personal protection equipment and (personal protection equipment means a NIOSH/MSHA approve respirator or gas mask fitted with an approved canister for phosphine. The canister is approved for use up to 15 ppm. SCBA or its equivalent must be used above 15 ppm or at unknown concentrations) and detection equipment. A person qualified in the use of this equipment must accompany the vessel with cargo under furnigation. Emergency procedures, cargo ventilation, periodic monitoring and inspections, and first aid measures must be discussed with and understood by the master of the vessel or his representative.
- 3. Seal all openings to the cargo hold or tank and lock or otherwise secure all openings, manways, etc. which might be used to lenter hold. The overspace pressure relief system of each tank aboard tankers

must be sealed by closing the appropriate valves and sealing the openings into the overspace with gastight materials.

- 4. Placard all entrances to the treated spaces with furnigation warning signs.
- 5. If the furnigation is not completed and the vessel aerated before the manned vessel leaves port, the person in charge of the vessel shall ensure that at least two units of personal protection equipment and one gas or vapor detection device, and a person qualified in their operation be on board the vessel during the voyage.
- 6. During the furnigation or until a manned vessel leaves port or the cargo is aerated, the person in charge of the furnigation shall ensure that a qualified person using gas or vapor detection equipment tests spaces adjacent to areas containing furnigated cargo and all regularly occupied spaces for furnigant leakage. If leakage of the furnigant is detected, the person in charge if the furnigation shall take action to correct the leakage, or shall inform the master of the vessel, or his representative of the leakage so that corrective action can be taken.
- 7. Review with the master, or his representative, the precautions and procedures for the voyage.

# c. Application Procedures For Bulk Dry Cargo Vessels and Tankers

- 1. Apply tablets, pellets or bags by scattering uniformly over the commodity surface product may shallow or deep probed into the commodity mass.
- 2. Immediately after application of the fumigant, close and secure all hatch covers, tank tops, butterworth valves, manways, etc.

# d.Intransit Fumigation of Containers Aboard Ships

Intransit fumigation of containers on ships is also governed by U.S Coast Guard Regulation 46 CFR 147A as modified by U.S. Coast Guard Special Permit 52-75. This permit which must be obtained prior to the fumigation is available from: U.S. Coast Guard, Hazardous Materials Branch, MTH-1, Washington, DC 20593-0001

Application procedures for fumigation of raw commodities or processed foods in containers and other transport vehicles are described in the DIRECTIONS FOR USE Section of the INVENTA Corporation Applicator's Manual.

# e. Precautions and Procedures During Voyage

- 1. Using appropriate gas detection equipment, monitor spaces adjacent to areas containing fumigated cargo and all regularly occupied areas for fumigant leakage. If leakage is detected, the area should be evacuated of all personnel, ventilated, and action taken to correct the leakage before allowing the area to be occupied.
- 2. Do not enter fumigated areas except under emergency conditions. If necessary to enter a fumigated area, appropriate personal protection equipment must be used. Never enter fumigated areas alone. At least one other person, wearing personal protection equipment, should be available to assist in case of an emergency.

#### f. Precautions and Procedures During Discharge

1. If necessary to enter holds prior to discharge, test spaces directly above grain surface for fumigant concentration, using appropriate gas detection and personal safety equipment. Do not allow entry to fumigant areas without personal safety equipment, unless fumigant concentrations are at safe levels, as indicated by a suitable detector.

#### 9. Fumigation of Barges

Barge furnigations are also regulated by U.S. Coast Guard regulation 46 CFR 147A as modified by U.S. Coast Guard Special Permit 2-75. This permit must be obtained prior to the furnigation is available from: U.S. Coast Guard, Hazardous Materials Branch, MTH-1, Washington, DC 20593-0001

Leaks are a common cause of failures in the treatment of commodities aboard barges. Carefully inspect all hatch covers prior to application of Quik-Fume and seal, if necessary. Notify consignee if the barge is to be furnigated intransit.

### 10. Fumigations in Small Sesiable Enclosures

Excellent results may be attained in the treatment of small enclosures since it is often possible to control the furnigation and also to make the enclosure virtually gas tight. Take care not to overdose during these furnigations. A single pellet will treat a space of from 1.4 to 10 cubic feet. From 6.9 to 50 cubic feet may be furnigated with a single Quik-Furne tablet or 1 Quik-Furne bag.

# 11. Treatment of Beehives, Supers And Other Beekeeping Equipment

Quik-Furne tablets, pellets and bags may used for the control of the greater wax moth in stored beshives, supers and other beekeeping equipment and for the destruction of bees, Africanized bees, and diseased bees including those infested with tracheal mittes and foulbroad. The recommended dosage for this use is 30-45 tablets, 150-225 pellets or 3 bags per 1000 cu. ft. Furnigations may be performed in chambers at atmospheric pressure, under tarpaulins, etc. by placing bags, tablets or pellets on trays or in moisture permeable envelopes. Do not add more than 2 tablets or 10 pellets to each envelope. Honey from treated hives or supers may only be used for bee food.

# 12. Burrowing Pest Control

# a. List of Burrowing Pests

Quik-Fume tablets, pellets and bags may be used out of doors only for the control of the following burrowing rodents and moles: Woodchucks and yellow-belly Marmots (Rockchucks), Prairie Dogs (except Utah Prairie Dogs), Norway and Roof Rats, Mice, Ground Squirrels, Moles, Voles, Gophers and Chipmunks.

#### b. Directions For Use

Add from one 1 to 4 Quik-Fume tablets, 5 to 20 pellets, or 2 to 6 bags to each burrow opening. Then seal tightly by shoveling soil over the entrance after first packing the opening with crumpled newspaper or something similar to prevent soil from covering the Quik-Fume and slowing its action. Subsurface tunnels or runways should be treated every 5 to 10 feet with a dose of 2 to 4 tablets, 10-20 pellets, and 2 to 6 bags. Use lower rates in smaller burrows in tight soils under moist soil conditions and higher rates in larger burrows in porous soils when soil moisture is low. Addition of several cups of water to the burrow prior to dosing with Quik-Fume may improve efficacy in some porous soils. Treat reopened furrows and fresh runways a second time 1 to 3 days after the initial treatment. Quik-Fume may be used out of doors only for control of burrowing pests. Do not use within 15 feet (5 meters) of inhabited structures. Do not apply to burrows which may open under or into occupied buildings. For use on all agricultural and non-cropland areas.

#### c. Environmental Hazards

This product is very highly toxic to wildlife. Non-target organisms exposed to phosphine gas in burrows will be killed. Do not apply directly to water or wetlands (swamps, bogs, marshes, and potholes). Do not contaminate water by cleaning of equipment or disposal of wastes.

## d. Endangered Species Restrictions

The use of any pesticide in a manner that may kill or otherwise harm an endangered or threatened species or adversely modify their habitat is a violation of Federal laws. The use of this product is controlled to prevent death or harm to endangered or threatened species that occur in the following counties or elsewhere in their range.

# STATE (REGIONAL U.S. FISH AND WILDLIFE OFFICE)

SPECIES - COUNTY (Unless Specified)

ARIZONA (Albuquerque, NM)

Blackfooted Ferret - Statewide

**CALIFORNIA** (Portland, OR)

- San Joaquin Kit-Fox Fresno, Kern, Kings, Merced, Monterey, San Benito, San Luis Obispo, Santa Barbara, Tulare, Ventura
- . Blunt-nosed Leopard Lizard Fresno, Kern, Kings, Madera, Merced, Tulare

COLORADO (Denver, CO)

Black-footed Ferret - Statewide

FLORIDA (Atlanta, GA)

Eastern Indigo Snake - Statewide

GEORGIA (Atlanta, GA)

Eastern Indigo Snake - Statewide

# KANSAS (Derwer, CO)

- Black-footed Ferret Statewide MONTANA (Deriver, CO)
- Black-footed Ferret Statewide NEBRASKA (Denver, CO)
- Black-footed Ferret Statewide NEW MEXICO (Albuquerque, NM)
- Black-footed Ferret Statewide NORTH DAKOTA (Deriver, CO)
- Black-footed Ferret Statewide OKLAHOMA (Albuquerque, NM)
- Black-footed Ferret Statewide
   SOUTH DAKOTA (Deriver, CO)
- Black-footed Ferret Statewide
  TEXAS (Albuquerque, NM)

   Black-footed Ferret Statewide
- Black-footed Ferret Statewide
   UTAH (Deriver, CO)
- Desert Tortoise Washington
- Black-footed Ferret Statewide

# WYOMING (Denver, CO)

Black-footed Ferret - Statewide

Use of this product in the above areas is prohibited without first contacting and obtaining permission from the Endangered Species Specialist in the regional offices of the U.S. Fish and Wildlife Service (FWS) nearest you.

- e. Special Local Restrictions
- 1. North Carolina Quik-Furne tablets, pellets, and bags may only be used for control of rats and mice in the state of North Carolina. Use against other pests is not permitted.
- 2. Oklahoma A special permit for black-tailed prairie dog control by poisoning is required in Oklahoma. Contact the Oklahoma State Department of Wildlife Conservation to obtain this permit.
- 3. Wisconsin A state permit is required for use of pesticides to control small mammals, except rats and mice. Contact your local Department of Natural Resources for information.
- 4. Indiana Use of Quik-Furne tablets, pellets, or begs for mole control is not legal in the state of Indiana.
- 5. Missouri A state permit is required for use of pesticide in Missouri to control small mammals, except rats and mice. Contact the Missouri Department of Conservation for information.
- 6. Kansas A special permit for black-tailed prairie dog control by poisoning is required in Kansas. Contact the Kansas Fish and Game Commission for information.
- 7. California Use of Quik-Fume tablets, pellets, and bags for chipmunk control is not legal in the state of California.

# Section 4

## **AFRATION OF FUMIGATED COMMODITIES**

#### A. Foods and Feeds

Tolerances for phosphine residues have been established at 0.1 ppm for animal feeds and 0.01 ppm for finished foods. To assure compliance with these tolerances, it is necessary to aerate these commodities for 48 hours prior to offering to the end use consumer.

# B. Tobacco

Tobacco must be aerated for at least three days (72 hours) when furnigated in hogshead and for at least two days (48 hours) when furnigated in other containers. Tobacco furnigated in containers with plastic liners will probably require longer aeration periods to reach 0.3 ppm.

#### C. Alternatives

As an alternative to these aeration periods, each container of a treated commodity may be analyzed for residues using accepted analytical methods. If residues are less than tolerance levels, the commodity may be shipped to the consumer regardless of the above holding periods.

# Section 5

# **PLACARDING OF FUMIGATED AREAS**

The applicator must placard or post all entrances to the furnigating area with signs bearing.

- 1. The signal word DANGER/PELIGRO and the SKULL AND CROSSBONES symbol in red.
- The statement "Area and/or commodity under fumigation, DO NOT ENTER/NO ENTRE".
- 3. The statement, "This sign may only be removed after the commodity is completely aerated (contains 0.3 ppm or less phosphine gas). If incompletely aerated commodity is transferred to a new site, the new site must also be placarded and workers must not be exposed to more than 0.3 ppm phosphine."
- 4. The date and time fumigation begins and is completed.
- 5. Name of furnigant used.
- 6. Name, address and telephone number of the applicator.

All entrances to a furnigated area must be placarded. Where possible, placards should be placed in advance of the furnigation in order to keep unauthorized persons away. For railroad hopper cars, placarding must be placed on both sides of the car near the ladders and next to the top hatches into which the furnigant is introduced.

Do not remove a placard until the treated commodity is completely acrated. To determine whether acration is complete, each furnigated site or vehicle must be monitored and shown to contain 0.3 ppm or less phophine gas in the air space around and, when feasible, in the mass of the commodity. If 0.3 ppm or less phosphine is detected, the placard may be removed. However, if more than 0.3 ppm is detected, the placard must be transferred with the commodity to the new site. Workers who transfer or handle incompletely acrated commodity must be informed and appropriate measures must be taken (i.e., ventilation or respiratory protection) to prevent exposures from exceeding 0.3 ppm phosphine. It is recommended that the person removing the placard be trained. Training should cover physical, chemical and toxicological properties of phosphine; how to take gas readings; the exposure limits for phosphine; and symptoms of and first aid treatment for poisoning.

# Section 6

# **PROTECTIVE CLOTHING**

Wear dry gloves of cotton or other material when handling unpackaged Quik-Fume tablets, petlets or bags. Wash hands thoroughly after use and before smoking or eating. Aerate used gloves and other contaminated clothing in a well ventilated area prior to laundering.

For approved respiratory equipment and detection devices contact:

Mine Safety Appliance, Co. 121 Gamma Drive P.O. Box 426 Pittsburgh, PA 15230 412-967-3000

# Section 7

# APPLICATOR AND WORKER EXPOSURE

Depending upon temperature and humidity, this product will release phosphine gas slowly upon exposure to moisture from the air. However, because of the potential for applicators and workers to be exposed to phosphine gas during fumidation, the following exposure limits and respiratory protection requirements apply.

Exposure to phosphine gas may not exceed 0.3 ppm measured as an 8 hour time-weighted average (TWA) for applicators and workers during application. Application is defined as the time period covering the opening of the first container, applying the appropriate dosage of furnigant and closing up the site to be furnigated. All persons in the treated site and in adjacent indoor areas are covered by this exposure standard. Engineering controls such as forced air ventilation should be the primary means used to meet this exposure standard.

If the fumigant is applied from outside of a confined or enclosed indoor area (for example, a railroad car or an automatic dispenser located outside of an enclosed indoor area), the applicator may apply the fumigant and immediately leave the area without being exposed to gas levels in excess of the standard. Therefore, neither monitoring nor respiratory protection equipment is needed during fumigation from outside an enclosed indoor area, such as addition of fumigant to automatic dispensing devices located outdoors, to burrows of rodents or moles away from buildings, to railroad cars located outside, etc.

If the applicator enters a confined or enclosed indoor area to fumigate, monitoring with a low level detection device is necessary. It is recommended that a sufficient number of readings must be taken where worker exposure is likely to occur in order to establish that the exposure standard is not exceeded. Adjacent indoor areas likely to be occupied, should be checked for leaks. If monitoring equipment is not available, on a farm and application cannot be done outside of a structure, an approved canister respirator must be worn during application from within an enclosed indoor area.

If an approved respirator is not available, application must be done from outside of the site to be furnigated. It is recommended that the applicator or employer document exposure readings in an operation log or manual for each furnigation site. Once exposures have been adequately characterized for a site, subsequent monitoring is not routinely required for each application. However, spot checks should be made, especially if conditions significantly change or if a garlic odor is detected. If 0.3 ppm or less phosphine is detected, no respiratory protection is required even if a garlic odor had been previously detected.

If the exposure limits cannot be met through engineering controls (such as forced air ventilation), a full-face canister respirator approved by NIOSH/MSHA for aluminum phosphide must be worn. This respirator may be used to <u>enter</u> an area with levels up to 15 ppm or to <u>escape</u> an area with levels up to 1500 ppm. Above these levels or where levels are unknown, a NIOSH/MSHA approved self-contained breathing apparatus (SCBA), positive air pressure type, must be used. The NIOSH/OSHA Pocket Guide, 8-85, DHEW/NIOSH 78-210 lists these and other types of approved respirators and their limits. A NIOSH/MSHA approved full-face canister respirator must be available on site if the fumigant is applied from within an enclosed indoor area. When the fumigant is applied from within an enclosed indoor area, a SCBA respirator must also be available either on site or locally such as at a fire station or rescue squad. The SCBA is needed in the event that a spill, leak or rescue situation arises where the level of phosphine gas exceeds 15 ppm or is unknown.

After application, exposure for any person may not exceed 0.3 ppm phosphine (maximum concentration). Such exposures may occur if the commodity or space under fumigation leaks, when treated commodity is transferred or handled, if someone reenters an unaerated or partially aerated space, etc. Monitoring should be performed as described above to assure that this exposure limit is not exceeded. If exposures cannot be reduced to acceptable levels, the same respiratory protection requirements apply as above.

Because phosphine gas is highly mobile and may penetrate seemingly gas-tight materials such as concrete and cinder block, adjacent indoor areas likely to be occupied must be checked for leaks. Sealing of the fumigated site and/or airflow in the occupied areas must be sufficient to meet the exposure limit of 0.3 ppm (maximum concentration).

A treated commodity does not necessarily need to be aerated immediately, as it may be desirable to store it for a long period without aeration. However, a space or commodity must be aerated to 0.3 ppm or less phosphine in the worker's breathing zone before reentry is allowed. Reentry at higher levels requires the use of an approved respirator (see approved respirators described above).

Worker exposure during storage, transfer and handling of a treated commodity (raw, processed or finished) is covered by the exposure limit of 0.3 ppm (maximum concentration). Monitoring must be conducted as previously described to prevent overexposure at any time during these activities.

For approved respiratory equipment and detection devices contact:

Mine Safety Appliance, Co. 121 Gamma Drive P.O. Box 426 Pittsburgh, PA 15230 412-967-3000

# Section 8

# STORAGE INSTRUCTIONS

Store Quik-Fume in a dry, well ventilated area away from heat under lock and key. Post as pesticide storage area. Do not contaminate water, food or feed by storing pesticides in the same areas used to store these commodities. Do not store in buildings where humans or domestic animals reside.

# Section 9 DISPOSAL INSTRUCTIONS

#### 1. GENERAL DISPOSAL STATEMENTS

Do not contaminate water, food or feed by storage or disposal.

Unreacted or partially reacted aluminum phosphide is acutely hazardous. Improper disposal of excess pesticides, or rinsate is a violation of Federal Law. If these wastes cannot be disposed of by use according to label instructions, contact your State Pesticide or Environmental Control Agency, or the Hazardous Waste representative at the nearest E.P.A. Regional Office for guidance. For specific instructions, refer to the SPILL AND LEAK PROCEDURES.

Some local and state waste disposal regulations may vary from the following recommendations. Disposal procedures should be reviewed with appropriate authorities to ensure compliance with local regulations. Contact your state Pesticide or Environmental Control Agency or Hazardous Waste Specialist at the nearest E.P.A. Regional Office for guidance.

Triple rinse flasi and stoppers with water. Then offer for recycling or reconditioning, or puncture and dispose of in a sanitary landfill, or by other procedures approved by state and local authorities. Rinsate may be disposed of in a sanitary sewer, sanitary landfill or by other approved procedures. It is also permissible to remove lids and expose empty flasks outdoors until residue in the flasks is reacted. Then puncture and dispose of in a sanitary landfill or other approved site, or by other procedures approved by state and local authorities.

If properly exposed, the residual dust remaining after a furnigation with aluminum phosphide will be grayishwhite and contain only a small amount of unreacted material. However, residual dust from incompletely exposed aluminum phosphide will require special care.

#### 2. DIRECTIONS FOR DISPOSAL OF SPENT RESIDUES FROM ALUMINUM PHOSPHIDE

In open areas, small amounts of completely spent residual dust may be disposed of on site by burial or by spreading over the land surface away from inhabited buildings. Spent residual dust, bags or other packaging containing spent aluminum phosphide may also be collected and disposed of at a sanitary landfill, incinerator or other approved sites or by other procedures approved by Federal, state or local authorities. For 2 to 3 kg (4 to 7 lbs) of spent dust from 2 to 3 flasks of aluminum phosphide may be collected for disposal

in a 1-gallon bucket. Larger amounts, up to about one-half case, may be collected in burlap, cotton or other types of porous cloth bags for transportation in an open vehicle to the disposal site. Do not collect dust from more than 7 flasks of tablets or 10 flasks of pellets (about 11kg or 25 lbs) in a single bag. Do not pile cloth bags together. Do not collect dust, bags or other types of packaging in large drums, dumpsters, plastic bags or other containers where confinement may occur.

3. DIRECTIONS FOR DEACTIVATION OF PARTIALLY SPENT RESIDUES FROM ALUMINUM PHOSPHIDE.

Confinement of partially spent residues in a closed container, or collection and storage of large quantiles of partially spent product may result in a fire hazard. Small amounts of phosphine may be given off from unreacted aluminum phosphide, and confinement of the gas may result in a flash.

Partially spent product must be deactivated further prior to ultimate disposal. This is especially true in cases of incomplete exposure which has resulted in so-called "green dust" or following a fumigation which has produced large quantities of partially spent material.

Residual dust from aluminum phoshide may be deactivated as follows using the "Wet Method":

Deactivating solution is prepared by adding the appropriate amount of low sudsing detergent or surface active agent to water in a drum or other suitable container. The container should be filled with deactivating solution to within a few inches of the top.

Residual product is poured slowly into the deactivating solution and stirred to thoroughly wet all of the spent aluminum phosphide. This must be done in the open air and not within an enclosed indoor area. Residue from aluminum phosphide tablets or pellets should be mixed into no less than about 10 gallons of water-detergent solution for each case of material used. Dispose of the deactivated residue-water suspension, with or without preliminary decanting, at a sanitary landfill or other suitable site approved by local authorities. Where permissible, the slurry may be poured into a storm sewer or out onto the ground.

Respiratory protection is required during wet deactivation of partially spent material. Do not cover the container holding the slurry at any time. Do not dispose of dust in a toilet. Do not allow quantities of dry product residue from aluminum phosphide to be collected or stored without deactivation.

# Section 10

## SPILL AND LEAK PROCEDURES

A spill, other than incidental to application or normal handling, may produce high levels of gas and, therefore, attending personnel must wear SCBA or its equivalent when the concentration of phosphine gas is unknown. Other NIOSH/MSHA approved respiratory protection may be worn if the concentration is known. Do not use water at any time to clean up a spill of aluminum phosphide. Water in contact with unreacted tablets or pellets will greatly accelerate the production of phosphine gas which could result in a toxic and/or fire hazard. Wear cotton gloves when handling pesticides.

Return all intact aluminum flasks to cardboard cases or other suitable packaging which has been properly marked according to DOT regulations. Notify consignee and shipper of damaged cases.

If aluminum flasks have been punctured or damaged to leak, the container may be temporarily repaired with aluminum tape or the aluminum phosphide may be transferred from the damaged flask to a sound metal container which should be sealed and properly labeled as aluminum phosphide. Transport the damaged containers to an area suitable for posticide storage for inspection. Further instructions and recommendations may be obtained, if required, from INVENTA Corporation.

if a spill has occurred which is only a few minutes old, collect the tablets and pellets and place them back into the original flasks, if they are intact, and stopper tightly. Place the collected tablets and pellets in a sound metal container if the original flasks are damaged. CAUTION: These flasks may flash upon opening at some later time.

If the age of the spill is unknown or if the tablets and pellets have been contaminated with soil, debris, water, etc. gather up the spillage and place it into small open buckets having a capacity no larger than about one gallon. Do not add more than about one flask of spilled material, 1 to 1.5 Kg (2 to 3 lbs), to the bucket. If on-site, wet deactivation is not feasible, these open containers should be transported in open vehicles to a suitable

area away from inhabited buildings. Wet deactivation may then be carried out as described in the STORAGE 274, 27 AND DISPOSAL Section of the INVENTA Companion Applications & Storage Companion Companion Companion (Companion Companion)

if the contaminated material is not completely reacted by exposure to atmospheric moisture, deactivate the product by the "Wet Method" as follows:

Deactivating solution is prepared by adding the appropriate amount of low sudsing detergent or surface active agent to water in a drum or other suitable container. A 2% solution or 4 cups in 30 gallons is suggested. The container should be filled with deactivating solution to within a few inches of the top.

The tablets or pellets are poured slowly into the deactivating solution and stirred to thoroughly wet all of the product. This should be oone in open air. Aluminum phosphide tablets or pellets should be mixed into no less than about 15 gallons of water-detergent solution for each case of spent material. Allow the mixture to stand, with occasional stirring, for about 36 hours. The resultant sturry will then be safe to dispose of.

Dispose of the slurry of disactivated material, with or without preliminary decanting, at a sanitary landfill or other suitable site approved by local authorities. Where permissible, this slurry may be poured into a storm sewer or out onto the ground.

Respiratory protection is required during wet deactivation of unexposed product. NEVER place pellets, tablets, or dust or other formulations in a closed container such as a dumpster, sealed drum, plastic bag, etc.. as flammable concentrations and a flash of phosphine gas are likely to develop.

# FOR ASSISTANCE CONTACT:

**INVENTA Corporation** 14 Phoenix Drive Mendham, NJ 07945 201-543-7239