

62719-167

10/24/2000

1/20

(Base label):

**RESTRICTED USE PESTICIDE**

For retail sale to and use only by Certified Applicators or persons under their direct supervision and only for those uses covered by the Certified Applicator's certification.

(logo) Dow AgroSciences LLC

**Equity\***

For termiticide pest control programs and for control of various pests in and around non-residential buildings and structures or various modes of transport, such as warehouses, ship holds, railroad boxcars, industrial plants, and food processing plants; and on turf.

Active Ingredient:

chlorpyrifos: O,O-diethyl O-(3,5,6-trichloro-2-pyridinyl)phosphorothioate .....	23.5%
Inert Ingredients .....	76.5%
Total .....	100.0%

Contains 2 pounds of chlorpyrifos per gallon.

Keep Out of Reach of Children

**CAUTION      PRECAUCION**

Precaucion al usuario: Si usted no lee inglés, no use este producto hasta que la etiqueta le haya sido explicada ampliamente.

**Precautionary Statements**

**Hazards to Humans and Domestic Animals**

Harmful If Swallowed, Inhaled Or Absorbed Through Skin

Avoid contact with skin, eyes, or clothing. Avoid breathing spray mist. Handle concentrate in a ventilated area. Wash thoroughly with soap and water after handling and before eating or smoking. Remove contaminated clothing and wash before reuse. Keep away from food, feedstuffs and water supplies.

**ACCEPTED**

OCT 24 2000

Under the Federal Insecticide, Fungicide, and Rodenticide Act, as amended, for the pesticide registered under EPA Reg. No. 62719-167

### **Personal Protective Equipment (Mixers and Loaders)**

**Mixers and loaders** must wear long-sleeved shirt and long pants, chemical resistant footwear plus socks, chemical-resistant gloves such as nitrile or butyl, and protective eyewear (goggles, a faceshield, or safety glasses with front, brow, and temple protection.) Mixers and loaders who do not use a mechanical system (such as an inline injector) to transfer the contents of this container must wear coveralls or chemical resistant apron in addition to the other required PPE.

In addition, all pesticide handlers (mixers, loaders and applicators) must wear a respiratory protection device (MSHA/NIOSH approved number TC-21C or TC-23C; or respirator with an organic-vapor removing cartridge and a prefilter approved for pesticides with MSHA/NIOSH approval number TC-14G; or supplied-air respirator with MSHA/NIOSH approval number TC-19C; or self-contained breathing apparatus (SCBA) with MSHA/NIOSH approval number TC-13F) and protective eyewear when working in a non-ventilated space.

**Note: See specific use directions for personal protective equipment (PPE) required for application of this product.**

### **First Aid**

**If swallowed:** Call a physician or Poison Control Center immediately. Do not induce vomiting. Do not give anything by mouth to an unconscious person.

**If on skin:** Immediately wash with plenty of soap and water. Get medical attention.

**If in eyes:** Flush with plenty of water for 15 minutes. Get medical attention.

**If inhaled:** Remove victim to fresh air and if not breathing give artificial respiration, preferably mouth to mouth. Get medical attention.

**Note to physician:** Chlorpyrifos is a cholinesterase inhibitor. Treat symptomatically. If exposed, plasma and red blood cell cholinesterase tests may indicate significance of exposure (baseline data are useful). Atropine, only by injection, is the preferable antidote. Oximes, such as 2-PAM/protopam, may be therapeutic if used early; however, use only in conjunction with atropine. In case of severe acute poisoning, use antidote immediately after establishing an open airway and respiration.

### **Environmental Hazards**

This pesticide is toxic to birds and wildlife, and extremely toxic to fish and aquatic organisms. Do not apply directly to water, to areas where surface water is present or to intertidal areas below the mean high water mark. Drift and runoff from treated areas may be hazardous to aquatic organisms in adjacent aquatic sites. Cover or incorporate spills. Do not contaminate water by cleaning of equipment or disposal of equipment wash waters.

### **Physical or Chemical Hazards**

**Do not use or store near heat or open flame.**

**Refer to label booklet for additional precautionary information and Directions for Use.**

**Notice:** Read the entire label. Use only according to label directions. **Before buying or using this product, read "Warranty Disclaimer" and "Limitation of Remedies" inside label booklet.**

In case of emergency endangering health or the environment involving this product, call 1-800-992-5994. If you wish to obtain additional product information, visit our web site at [www.dowagro.com](http://www.dowagro.com).

**Agricultural Chemical:** Do not ship or store with food, feeds, drugs or clothing.

EPA Reg. No. 62719-167

EPA Est. 464-MI-1

\*Trademark of Dow AgroSciences LLC  
**Dow AgroSciences LLC • Indianapolis, IN 46268 U.S.A.**

3/20

# Specialty Termiticide Concentrate

Net Contents \_\_ gal

4/20

(Datapack cover):

**RESTRICTED USE PESTICIDE**  
 For retail sale to and use only by Certified Applicators or persons under their direct supervision and only for those uses covered by the Certified Applicator's certification.

(logo) Dow AgroSciences LLC

# Equity\*

**For termiticide pest control programs and for control of various pests in and around non-residential buildings and structures or various modes of transport, such as warehouses, ship holds, railroad boxcars, industrial plants, and food processing plants; and on turf.**

Active Ingredient:

chlorpyrifos: O,O-diethyl O-(3,5,6-trichloro-2-pyridinyl)phosphorothioate .....	23.5%
Inert Ingredients .....	76.5%
Total .....	100.0%

Contains 2 pounds of chlorpyrifos per gallon.

**Keep Out of Reach of Children**

## CAUTION      PRECAUCION

**Precaucion al usuario:** Si usted no lee inglés, no use este producto hasta que la etiqueta le haya sido explicada ampliamente.

**Refer to label booklet for additional precautionary information and Directions for Use.**

**Notice:** Read the entire label. Use only according to label directions. **Before buying or using this product, read "Warranty Disclaimer" and "Limitation of Remedies" inside label booklet.**

In case of emergency endangering health or the environment involving this product, call 1-800-992-5994. If you wish to obtain additional product information, visit our web site at [www.dowagro.com](http://www.dowagro.com).

Agricultural Chemical: Do not ship or store with food, feeds, drugs or clothing.

EPA Reg. No. 62719-167

EPA Est. 464-MI-1

\*Trademark of Dow AgroSciences LLC  
 Dow AgroSciences LLC • Indianapolis, IN 46268 U.S.A.

## Specialty Termiticide Concentrate

Net Contents \_\_\_ gal

5/20

(Page 1 through end):

<b>Table of Contents</b>	<b>Page</b>
Precautionary Statements	-
Hazards to Humans and Domestic Animals	-
Personal Protective Equipment (Mixers and Loaders)	-
First Aid	-
Environmental Hazards	-
Physical or Chemical Hazards	-
Directions for Use	-
Storage and Disposal	-
Wood Destroying Insects	-
Subterranean Termites	-
Applicator PPE for Termiticide Uses	-
Important Use Limitations	-
Postconstruction Use	-
Preconstruction Use	-
General Use Precautions	-
Rate Determination Guidelines	-
Dilution Directions	-
Mixing Directions	-
Application Volume	-
Retreatment Statement	-
Structures with Wells/Cisterns Inside Foundations	-
Structures with Adjacent Wells/Cisterns and/or Other Water Bodies	-
Preconstruction Subterranean Termite Treatment	-
Postconstruction Treatments	-
Use Limitations on Postconstruction Application	-
Treatment of Active Termite Infestations	-
Preventative Use	-
Underground Utility Cable and Conduit (Non-residential)	-
Utility Poles and Fence Posts (Non-residential)	-
General Pest Control - Perimeter Treatments (Industrial Plant Sites Only)	-
Directions for Perimeter Treatments	-
Applicator PPE for Perimeter Treatments	-
Precautions for Perimeter Treatments	-
Treatment Sites	-
Dosage Rates	-
Mixing Directions	-
Tank Mixing	-
Application Methods	-
Low Volume Directed Sprays	-
High Volume Broadcast Sprays	-
Pests Controlled by Perimeter Treatments of Equity	-
Specific Use Directions for Perimeter Treatments	-
Non-residential Turfgrass Areas (Including Golf Courses, Road Medians and Industrial Plant Sites)	-
Warranty Disclaimer	-
Inherent Risks of Use	-
Limitation of Remedies	-

6/20

---

## Precautionary Statements

---

### Hazards to Humans and Domestic Animals

# CAUTION

#### Harmful If Swallowed, Inhaled Or Absorbed Through Skin

Avoid contact with skin, eyes, or clothing. Avoid breathing spray mist. Handle concentrate in a ventilated area. Wash thoroughly with soap and water after handling and before eating or smoking. Remove contaminated clothing and wash before reuse. Keep away from food, feedstuffs and water supplies.

#### Personal Protective Equipment (Mixers and Loaders)

Mixers and loaders must wear long-sleeved shirt and long pants, chemical resistant footwear plus socks, chemical-resistant gloves such as nitrile or butyl, and protective eyewear (goggles, a faceshield, or safety glasses with front, brow, and temple protection.) Mixers and loaders who do not use a mechanical system (such as an inline injector) to transfer the contents of this container must wear coveralls or chemical resistant apron in addition to the other required PPE.

In addition, all pesticide handlers (mixers, loaders and applicators) must wear a respiratory protection device (MSHA/NIOSH approved number TC-21C or TC-23C; or respirator with an organic-vapor removing cartridge and a prefilter approved for pesticides with MSHA/NIOSH approval number TC-14G; or supplied-air respirator with MSHA/NIOSH approval number TC-19C; or self-contained breathing apparatus (SCBA) with MSHA/NIOSH approval number TC-13F) and protective eyewear when working in a non-ventilated space.

**Note:** See specific use directions for personal protective equipment (PPE) required for application of this product.

#### First Aid

**If swallowed:** Call a physician or Poison Control Center immediately. Do not induce vomiting. Do not give anything by mouth to an unconscious person.

**If on skin:** Immediately wash with plenty of soap and water. Get medical attention.

**If in eyes:** Flush with plenty of water for 15 minutes. Get medical attention.

**If inhaled:** Remove victim to fresh air and if not breathing give artificial respiration, preferably mouth to mouth. Get medical attention.

**Note to physician:** Chlorpyrifos is a cholinesterase inhibitor. Treat symptomatically. If exposed, plasma and red blood cell cholinesterase tests may indicate significance of exposure (baseline data are useful). Atropine, only by injection, is the preferable antidote. Oximes, such as 2-PAM/protopam, may be therapeutic if used early; however, use only in conjunction with atropine. In case of severe acute poisoning, use antidote immediately after establishing an open airway and respiration.

#### Environmental Hazards

This pesticide is toxic to birds and wildlife, and extremely toxic to fish and aquatic organisms. Do not apply directly to water, to areas where surface water is present or to intertidal areas below the mean high water mark. Drift and runoff from treated areas may be hazardous to aquatic organisms in adjacent aquatic sites. Cover or incorporate spills. Do not contaminate water by cleaning of equipment or disposal of equipment wash waters.

#### Physical or Chemical Hazards

**Do not use or store near heat or open flame.**

7/20

---

### Directions for Use

---

It is a violation of Federal law to use this product in a manner inconsistent with its labeling. Read all Directions for Use carefully before applying.

**Do not tank mix this product with products containing dichlorvos (DDVP).**

**Do not formulate this product into other end-use products.**

### Storage and Disposal

Do not contaminate water, food or feed by storage or disposal.

**Storage:** Store in original container in secured dry storage area. Prevent cross-contamination with other pesticides and fertilizers. Avoid storing above 122°F for extended periods of time. Storage below 40° F may result in formation of crystals. If product crystallizes, store at 55-75°F and shake occasionally to redissolve crystals. If container is damaged or spill occurs, use product immediately or dispose of product and damaged container as indicated below.

**Pesticide Disposal:** Pesticide wastes are toxic. Improper disposal of excess pesticide, spray mixture, or rinsate is a violation of Federal law. If these wastes cannot be disposed of by use according to label instructions, contact your state pesticide or environmental control agency, or the hazardous waste representative at the nearest EPA regional office for guidance.

**Container Disposal for Non-refillable Containers:** Triple rinse (or equivalent) then offer for recycling or reconditioning, or puncture and/or crush rinsed, empty container and dispose of in a sanitary landfill, or other procedures approved by state and local authorities.

or

Triple rinse (or equivalent). Then dispose of in a sanitary landfill or by incineration, or, if allowed by state and local authorities, by burning. If burned, stay out of smoke.

**Container Disposal for Refillable Containers:** Replace the dry disconnect cap, if applicable, and seal all openings which have been opened during use. Return the empty container to a collection site designated by Dow AgroSciences. If the container has been damaged and cannot be returned according to the recommended procedures, contact Dow AgroSciences Customer Service Center at 1-800-258-1470 to obtain proper handling instructions.

---

### Wood Destroying Insects

---

#### Subterranean Termites

Equity\* termiticide concentrate for soil treatment is used to establish a barrier which is lethal to termites. In order to provide an effective barrier between the wood in the structure and termite colonies in the soil, disperse the chemical emulsion so as to avoid untreated gaps in the barrier.

#### Applicator PPE For Termiticide Uses

- **Pesticide Applicators** must wear long-sleeved shirt and long pants, socks, shoes, and chemical-resistant gloves. In addition, pesticide applicators must wear protective eyewear when applying termiticide by rodding or sub-slab injection.
- In addition, a respiratory protection device (MSHA/NIOSH approved number TC-21C or TC-23C; or respirator with an organic-vapor removing cartridge and a prefilter approved for pesticides with MSHA/NIOSH approval number TC-14G; or supplied-air respirator with MSHA/NIOSH approval number TC-19C; or self-contained breathing apparatus (SCBA) with MSHA/NIOSH approval number TC-13F) and protective eyewear must be worn when working in a non-ventilated space.

It is important that the service technician be familiar with current control practices including trenching, rodding, subslab injection, and low pressure spray applications. These techniques must be correctly employed to prevent or control infestations by subterranean termite species of *Reticulitermes*, *Zootermopsis*, *Heterotermes*, and *Coptotermes*. Choice of appropriate procedures includes consideration of such variable factors as the design of the structure, water table, soil type, soil compaction, grade conditions, and the location and type of domestic water supplies. The biology and behavior of the involved

8/20

termite species are important factors to be known as well as suspected location of the colony and severity of the infestation within the structure to be protected. For advice concerning current control practices for specific local conditions, consult resources in structural pest control.

**Important Use Limitations**

**Postconstruction Use:** For use outside structures only. For postconstruction use, this product may be applied only as spot or local barrier treatments with a maximum end-use dilution of 0.5%. Spot treatments not to exceed 25% of the amount required to treat the entire structure at the label rate. Areas treated must be inspected annually for signs of reinfestation. Postconstruction applications may be made until December 31, 2002. Thereafter, postconstruction use of this product is prohibited.

**General Use Precautions (Additional Precautionary Statements)**

All nonessential wood and cellulose containing materials, including scrap wood and form boards, should be removed from around foundation walls, crawl spaces, and porches. This does not include existing structural soil contact wood that has been treated.

When treating adjacent to an existing structure, the applicator must check the areas to be treated, and immediately adjacent areas of the structure for visible and accessible cracks and holes to prevent any leaks or significant exposures to persons occupying the structure. People present or residing in the structure during application must be advised to remove their pets and themselves from the structure if they see any signs of leakage. After application, the applicator is required to check for leaks.

All leaks resulting in the deposition of termiticide in locations other than those prescribed on this label must be cleaned up prior to leaving the application site. Do not allow people or pets to contact contaminated areas or to reoccupy the contaminated areas of the structure until the cleanup is completed.

Contamination of public and private water supplies must be avoided by following these minimum precautions:

1. Use anti-backflow equipment or procedures to prevent siphonage of pesticide back into water supplies.
2. Do not treat soil that is water saturated or frozen.
3. Do not treat while precipitation is occurring.
4. Consult Federal, state, and local specifications for information regarding approved treatment practices in your area.
5. Do not contaminate wells or cisterns. See specific "Treatment of Structures with Wells, Cisterns or Other Bodies of Water Adjacent to Treated Sites".

**Rate Determination Guidelines**

- A dilution rate of 0.5% is required for all termiticide applications.
- A 1.0% to 2.0% dilution may be used to protect underground utility cable and conduit and utility poles and fence posts in non-residential areas.

**Table 1: Dilution Directions**

Gallons of Finished Dilution Desired	Amount of Equity Needed		
	0.5%	1.0%	2.0%
1	2.7 fl oz	5.3 fl oz	10.7 fl oz
5	13.3 fl oz	26.7 fl oz	53.4 fl oz
10	26.7 fl oz	53.4 fl oz	107 fl oz
24	0.5 gal	1 gal	2 gal
48	1 gal	2 gal	4 gal
97	2 gal	4 gal	8 gal

**Mixing Directions**



9/20

It is important that the termiticide dilution be uniformly mixed in the spray tank before and during beginning the treatment. The initial mixing will be enhanced by agitation, circulation through the treating hose, and the filling process. By-pass, jet, or mechanical agitation will ensure that the dilution remains uniformly mixed during application.

1. Fill tank 1/4 to 1/3 full.
2. Start pump to begin by-pass agitation and place end of treating tool in tank to allow circulation through hose.
3. Add appropriate amount of Equity.
4. Add remaining amount of water.
5. Let pump run and allow recirculation through the hose for 2 to 3 minutes.

#### **Application Volume**

To provide maximum control and protection against termite infestation, apply the specified volume of the finished water emulsion and active ingredient as set forth in the Directions for Use section of this label. If soil will not accept the labeled application volume, such as heavy, clay-type soils, the volume may be reduced provided there is a corresponding increase in concentration so that the amount of active ingredient applied to the soil remains the same. This would also apply to sensitive areas and/or horizontal applications where less volume may be desirable. Minimum volumes will be specified in the appropriate use directions. In light textured soils such as sand or gravel that accept larger amounts of water, increased volumes that deliver the appropriate concentration of termiticide in the soil may be used. Maximum volumes will be specified in the appropriate use directions. Note: Large reductions of application volume reduce the ability to obtain a continuous barrier. Variance is allowed when volume and concentration are consistent with label directed rates and a continuous barrier can still be achieved.

#### **Retreatment Statement**

Retreatment for subterranean termites can only be performed if there is clear evidence of reinfestation or disruption of the barrier due to construction, excavation, or landscaping and/or evidence of the breakdown of the termiticide barrier in the soil. These vulnerable or reinfested areas may be retreated in accordance with application techniques described in this product's labeling. The timing and type of these retreatments will vary, depending on factors such as termite pressure, soil types, soil conditions and other factors which may reduce the effectiveness of the barrier.

Annual retreatment of the structure is prohibited unless there is clear evidence that reinfestation or barrier disruption has occurred.

#### **Treatment of Structures with Wells, Cisterns or Other Bodies of Water Within or Adjacent to Treated Sites**

Do not contaminate wells or cisterns.

1. **Structures With Wells/Cisterns Inside Foundations:** Structures that contain wells or cisterns within the foundation of a structure can only be treated using the following techniques:
  - a. Do not treat soil while it is beneath or within the foundation or along the exterior perimeter of a structure that contains a well or cistern. The treated backfill method may be used if soil is removed and treated outside/away from the foundation. The treated backfill technique is described as follows:
    - (1) Trench and remove soil to be treated onto heavy plastic sheeting or similar material or into a wheelbarrow.
    - (2) Treat the soil at the rate of 4 gallons of dilute emulsion per 10 linear feet per foot of depth of the trench, or 1 gallon per 1.0 cubic feet of soil. See "mixing Directions" section of this label. Mix thoroughly into the soil taking care to contain the liquid and prevent runoff or spillage.

10/20

- (3) After the treated soil has absorbed the diluted emulsion, replace the soil into the trench.
  - b. Infested and/or damaged wood in place may be treated using an injection technique such as described in the "Control of Wood Infesting Insects" section of this label.
2. **Structures With Adjacent Wells/Cisterns and/or Other Water Bodies:** Applicators must inspect all structures with nearby water sources such as wells, cisterns, surface ponds, streams, and other bodies of water and evaluate, at a minimum, the treatment recommendations listed below prior to making an application.
- a. Prior to treatment, if feasible, expose the water pipe(s) coming from the well to the structure, if they enter the structure within 3 feet of grade.
  - b. Prior to treatment, applicators are advised to take precautions to limit the risk of applying the termiticide into subsurface drains that could empty into any bodies of water. These precautions include evaluating whether application of the termiticide to the top of the footer may result in contamination of the subsurface drain. Factors such as depth to the drain system and soil type and degree of compaction should be taken into account in determining the depth of treatment.
  - c. When appropriate (i.e., on the water side of the structure), the treated backfill technique (described above) can also be used to minimize off-site movement of termiticide.

#### **Preconstruction Subterranean Termite Treatment**

**Areas treated with 0.5% or less must be reinspected annually for signs of reinfestation.**

**Preconstruction applications are defined as those applications made prior to the finished grade being installed.** Effective Preconstruction treatment for subterranean termite prevention requires the establishment of vertical and/or horizontal chemical barriers between wood in the structure and the termite colonies in the soil. To meet FHA termite proofing requirements, follow the latest edition of the Housing and Urban Development (HUD) Minimum Property Standards. Follow state and local regulations to meet minimum treatment standards for preventive Preconstruction treatments.

**Do not apply at a lower dosage and/or concentration than specified on this label for applications prior to installation of the finished grade.**

Prior to each application, applicators must notify the general contractor, construction superintendent, or similar responsible party, of the intended termiticide application and intended sites of application and instruct the responsible person to notify construction workers and other individuals to leave the area to be treated during application and until the termiticide is absorbed into the soil.

See "Rate Determination Guidelines" and "Table 1" for dilution directions.

1. For **horizontal barriers**, applications shall be made using a low pressure spray (not to exceed 50 psi when measured at the treating tool to minimize exposure and potential for drift) after grading is completed and prior to the pouring of the slab or footing.
  - a. Apply 1 gallon of the 0.5% end-use dilution per 10 square feet or use 2.6 fluid ounces of Equity per 10 square feet in sufficient water (no less than 1/2 gallon or more than 2 gallons) to provide thorough and continuous coverage of the area being treated (See Application Volume section).

If the fill is washed gravel or other coarse material, it is important that a sufficient amount of dilution be used to reach the soil substrate beneath the coarse fill.

- b. If concrete slabs cannot be poured over the soil the same day it has been treated, a vapor barrier should be placed over the treated soil to prevent disturbance of the termiticide barrier.
2. For **vertical barriers**, apply the 0.5% end-use dilution at a rate of 4 gallons per 10 linear feet per foot of depth. Establish vertical barriers in areas such as around foundations, plumbing lines, backfilled soil against foundation walls and other areas that may warrant more than just a horizontal barrier.
    - a. When treating foundations deeper than 4 feet, apply the termiticide as the backfill is being replaced, or if the construction contractor fails to notify the applicator to permit this, treat the foundation to a minimum depth of 4 feet after the backfill has been installed. The applicator must trench and rod into the trench or trench along the foundation walls and around pillars and other foundation elements, at the rate prescribed from grade to a minimum depth of 4 feet. When the top of the footing is exposed, the applicator must treat the soil adjacent to the footing to a depth not to exceed the bottom of the footing. However, in no case should a structure be treated below the footing.
    - b. Trenches need not be wider than 6 inches. Treat soil with the dilution as it is being replaced in the trench.

Apply 4 gallons of the 0.5% end-use dilution per 10 linear feet per foot of depth or 10 2/3 fluid ounces of Equity per 10 linear feet per foot of depth from grade to top of footing in sufficient water (not less than 2 gallons or more than 8 gallons) to ensure complete coverage.
    - c. Hollow block foundations or voids of masonry can be treated to make a complete chemical barrier especially if the soil was not treated prior to pouring the footing. Apply the dilution at a rate of 2 gallons per 10 linear feet so that it reaches the top of the footing.
    - d. For crawl spaces, establish a vertical barrier on both sides of the foundation and around all piers and areas where underground utilities exit the soil. Do not apply the dilution to the entire surface area intended as the crawl.
  3. For **plenum type structures** which use a sealed underfloor space to circulate heated and/or cooled air throughout the structure. Apply the 0.5% end-use dilution at a rate of 4 gallons per 10 linear feet per foot of depth. Soil adjacent to both sides of foundation walls, supporting piers, plumbing and conduits should be treated by trenching or rodding (where soil conditions permit) to a depth of 6 inches or, if less shallow, to the top of the footing. When conditions will not permit trenching or rodding, surface application adjacent to interior foundation walls may be made but the treated strip shall not exceed a width of 18 inches, horizontally, from the foundation walls, piers, or pipes. The surface application should be made at a rate of 1 gallon per 10 square feet as a very coarse spray under low pressure (not to exceed 20 p.s.i. when measured at the treating tool). After soil treatment, a continuous vapor barrier of at least 6 mil polyethylene film or other suitable vapor barrier must be installed on the ground surface over the entire subfloor area and on the inside of the plenum walls, in accordance with the recommended practice for plenum type structures.

## Postconstruction Treatments

**Postconstruction applications** are defined as those applications made after the final grade is installed.

**Use Limitations on Postconstruction Application:** Post construction use of this product is limited to local and spot applications (see "Important Use Limitations" section at the beginning of the "Directions for Use" section). Spot or local treatments may be used to control active termite infestations or used preventatively. Complete barrier treatments for postconstruction application are prohibited.

**Treatment of Active Termite Infestations:** Spot and local application of this product must be limited to portions of the structure containing active termite infestations and underlying soil containing nesting sites. The extent of treatment must be limited to portions of the structure necessary to bring an existing termite infestation under control. When used as a spot or local application, it is recommended that Equity be used in conjunction with the Sentricon® Colony Elimination System as part of an integrated pest management program to ensure continued protection of the entire structure.

**Preventative Use:** Preventative use is recommended in conjunction with the use of the Sentricon® Colony Elimination System as a part of the integrated pest management (IPM) program for control of subterranean termites. As a preventative treatment, Equity may be use as a spot or local application in critical areas of the structure including plumbing and utility entry sites, bath traps, expansion joints, foundation cracks or other areas where termites may find entry or infestation is suspected.

See "Rate Determination Guidelines" and "Table 1" for dilution directions.

**Precaution:** Do not apply dilution until location of heat or air conditioning ducts, vents, water and sewer lines and electrical conduits are known and identified. Extreme caution must be taken to avoid contamination of these structural elements and airways.

All holes in commonly occupied areas into which material has been applied must be plugged. Plugs should be of a non-cellulose material or covered by an impervious, non-cellulose material.

1. For **slab-on-ground construction** applications may be made using techniques such as sub-slab injection, rodding and/or trenching. Injectors should not extend beyond the tops of the footings.
  - a. Treat along the outside of the foundation to form a continuous termiticide barrier in the soil.

For shallow foundations, 1 foot or less, dig a narrow trench approximately 6 inches wide along the outside of the foundation walls. Do not dig below the bottom of the footings. For foundations with exposed footings, dig a trench alongside the footing taking care not to undermine the footing. The dilution should be applied to the trench and mixed with the soil as it is replaced in the trench.

Apply 4 gallons of the 0.5% end-use dilution per 10 linear feet or use 10 2/3 fluid ounces of Equity per 10 linear feet in sufficient water (no less than 2 gallons or more than 8 gallons) to provide thorough and complete coverage of the area being treated (See "Application Volume").

For foundations with footings deeper than 1 foot, apply the 0.5% end-use dilution at a rate of 4 gallons per 10 linear feet per foot of depth. For applications made after the final grade is installed, the applicator must trench and rod into the trench or trench along the foundation walls and around pillars and other foundation elements at the rate prescribed from grade to the top of the footing. When the footing is more than 4 feet below grade, the applicator must trench and rod into the trench or trench along the foundation wall at the rate prescribed to a minimum depth of 4 feet. The actual depth of treatment will vary depending on soil type, degree of compaction, and location of termite activity. When the

13/20

top of the footing is exposed, the applicator must treat the soil adjacent to the footing to a depth not to exceed the bottom of the footing. However, in no case should a structure be treated below the footing.

- b. When treating cracks and expansion joints in the slab, along sidewalks or patios adjacent to the exterior foundation wall or other areas where holes are to be drilled to form a continuous termiticide barrier, the holes should be spaced at intervals up to 24 inches depending on soil type.

Hard, dry soils typically allow good lateral (horizontal) dispersion. However, they may be slow in absorption or downward movement. Care must be taken when injecting through slabs into areas with this type of soil. Low pressures should be considered in this situation. This will help to avoid backsplashing from the injection hole, backflow from cracks and expansion joints, and unwanted emergence of the termiticide dilution from adjacent drill holes. A slow, low pressure application using the proper volume of termiticide dilution will allow the soil to absorb the liquid and provide an adequate vertical barrier. The wider drill hole spacing (18 to 24 inches) can usually be used in this situation. Sand, loam, or gravel backfill materials are commonly found under slab foundations. The type of fill, amount of settling that has occurred, moisture content, etc., will determine drill hole spacing and amount of termiticide dilution to be injected through each hole. Highly absorptive soils or those with large pore spaces (gravel, coarse sand) will afford rapid downward (vertical) movement and limited lateral (horizontal) distribution of the termiticide dilution. In this situation, consider using a lateral dispersion tip on the sub-slab injector and place the drill holes closer together (12 to 18 inches). Apply 4 gallons of the 0.5% end-use dilution per 10 linear feet.

- c. It may be necessary to treat along one side of interior partition walls if there are cracks in the slab, plumbing entry points, existing termite infestations, or other conditions which would make treatment appropriate.
- d. To form a termiticide barrier under slab foundations, it may be necessary to drill and treat near plumbing and electrical entry areas, cracks, or other areas where termites might enter the structure. In this instance, one or more holes should be drilled in the slab as close to the entry point as is practical and termiticide placed in the fill. As a general rule, 3 to 5 gallons of dilution per entry point will usually give adequate coverage, however, the use of directional or lateral dispersion tips or foam delivery systems can give adequate coverage with lower volumes. Location of the drill hole in relation to the entry point, type of soil fill, presence or absence of a vapor barrier, application pressure and other considerations will affect the coverage and volume of termiticide needed to form a complete barrier. Precautions must be taken to avoid drilling into plumbing or electrical conduit.
- e. When necessary, drill through the foundation walls from the outside and force the dilution just beneath the slab either along the inside of the foundation or along all the cracks and expansion joints and other critical areas.
- f. **Bath traps:** Exposed soil or soil covered with tar or a similar type sealant beneath and around plumbing and/or drain pipe entry areas may be treated with a the 0.5% end-use dilution of Equity.

An access door or inspection vent should be cut and installed, if not already present. After inspection and removal of any wood or cellulose debris, the soil can be treated by rodding or drenching the soil. A one square foot bath trap will usually require about 3 to 5 gallons of dilution for thorough and complete coverage.

14/20

2. **Hollow block foundations or voids in masonry** resting on the footing can be treated to make a continuous chemical barrier in the voids. If the void has direct contact with the soil, it should be treated. Drill and treat all voids in multiple masonry elements of the structure extending from the structure to the soil in order to create a continuous treatment barrier in the area to be treated. Apply at the rate of 2 gallons of emulsion per 10 linear feet of footing using a nozzle pressure of less than 25 psi. When using this treatment access holes must be drilled below the sill plate and should be as close as possible to the footing as is practical. Treatment of voids in block or rubble foundation walls must be closely examined. Applicators must inspect areas of possible runoff as a precaution against application leakage in the treated areas. Some areas may not be treatable or may require mechanical alteration prior to treatment.

Not for use in voids insulated with rigid foam.

3. For **basements**, apply at a rate of 4 gallons of dilution per 10 linear feet per foot of depth. Where footings are greater than 1 foot of depth from the grade to the top of the footing, application may be made by trenching and/or rodding at a rate of 4 gallons of dilution per 10 linear feet per foot of depth. When the footing is more than 4 feet below grade, the applicator must trench and rod into the trench or trench along the foundation wall at the rate prescribed to a minimum depth of 4 feet. The actual depth of treatment will vary depending on soil type, degree of compaction, and location of termite activity. When the top of the footing is exposed, the applicator must treat the soil adjacent to the footing to a depth not to exceed the bottom of the footing. However, in no case should a structure be treated below the footing. Treat outside of foundation walls, and if necessary beneath the basement floor along inside of foundation walls, along cracks in basement floors, along interior load bearing walls, around sewer pipes, conduits and piers.
4. **Accessible Crawl Spaces:** For crawl spaces, apply vertical termiticide barriers at the rate of 4 gallons of emulsion per 10 linear feet per foot of depth from grade to top of footing, or if the footing is more than 4 feet below grade, to a minimum depth of 4 feet.

Apply 4 gallons of the 0.5% end-use dilution per 10 linear feet per foot of depth or 5 1/3 fluid ounces of Equity per 10 linear feet per foot of depth from grade to top of footing in sufficient water (not less than 2 gallons or more than 8 gallons) to ensure complete coverage.

Apply by trenching and rodding into the trench, or trenching. Treat both sides of foundation and around all piers and pipes. Where physical obstructions, such as concrete walkways adjacent to foundation elements, prevent trenching, treatment may be made by rodding alone. When soil type and/or conditions make trenching prohibitive, rodding may be used. When the top of the footing is exposed, the applicator must treat the soil adjacent to the footing to a depth not to exceed the bottom of the footing. Read and follow the mixing and use direction section of the label if situations are encountered where the soil will not accept the full application volume.

- a. Rod holes and trenches shall not extend below the bottom of the footing.
  - b. Rod holes shall be spaced so as to achieve a continuous chemical barrier but in no case more than 12 inches apart.
  - c. Trenches shall be a minimum of 6 inches deep or to the bottom of the footing, whichever is less, and need not be wider than 6 inches. When trenching in sloping (tiered) soil, the trench shall be stepped to ensure adequate distribution and to prevent termiticide from running off. The emulsion must be mixed with the soil as it is replaced in the trench.
  - d. When treating crawl spaces, turn off the air circulation system of the structure until application has been completed and all termiticide has been absorbed by the soil.
5. **Inaccessible Crawl Spaces:** For inaccessible interior areas, such as areas where there is insufficient clearance between floor joists and ground surfaces to allow operator access, excavate

if possible, and treat according to the instructions for accessible crawl spaces. Otherwise, apply one or a combination of the following two methods.

Apply 4 gallons of the 0.5% end-use dilution per 10 linear feet or 10 2/3 fluid ounces of Equity per 10 linear feet in sufficient water (not less than 2 gallons or more than 8 gallons) to ensure complete coverage (See "Application Volume").

- a. To establish a horizontal barrier, apply 1 gallon of emulsion per 10 sq ft to the soil surface. Use a nozzle pressure of less than 25 psi. and a coarse application nozzle (e.g., Delavan Type RD Raindrop, RD-7 or larger, or Spraying Systems Co. 8010LP TeeJet or comparable nozzle). For an area that cannot be reached with the application wand, use one or more extension rods to make the application to the soil. Do not broadcast or powerspray with higher pressures.
- b. To establish a horizontal barrier, drill through the foundation wall or through the floor above and treat the soil perimeter at a rate of 1 gallon of emulsion per 10 square feet. Drill spacing must be at intervals not to exceed 16 inches. Many states have smaller intervals so check state regulations that may apply.

When treating crawl spaces, turn off the air circulation system of the structure until application has been completed and all termiticide has been absorbed by the soil.

- c. In the presence of unsupported termite tubes, mechanically destroy each tube and apply approximately 1 pint of the 0.5% end-use dilution to an area of no more than 18 inches in diameter where the tubes emerged from the soil.
6. In **plenum type structures** which use a sealed underfloor space to circulate heated and/or cooled air within the structure, turn off the air circulation system of the structure until application has been completed and all termiticide has been absorbed by the soil.. Apply the 0.5% end-use dilution at a rate of 4 gallons per 10 linear feet per foot of depth. Soil adjacent to both sides of the foundation walls, supporting piers, plumbing and conduits should be treated by trenching or rodding (where soil conditions permit) to a depth of 6 inches or to the top of the footing. When conditions will not permit trenching or rodding, a surface application adjacent to interior foundation walls may be made, but the treated strip shall not exceed a width of 18 inches, horizontally, from the foundation piers or pipes. Surface application is made at a rate of 1 gallon per 10 square feet as a very coarse spray under low pressure (not to exceed 20 p.s.i. when measured at the treating tool). In order to properly calculate the amount of termiticide dilution needed, use the following guideline: A strip 18 inches wide and 6 feet 8 inches long is equal to 10 square feet. Before treatment, a barrier of at least 6 mil polyethylene film or other suitable vapor barrier must be present on this ground surface over the entire subfloor area in accordance with recommended practices for plenum type structures. Install a new vapor barrier if barrier is absent or deteriorated. The vapor barrier film on the ground and foundation walls must be folded back from the areas to be treated prior to treatment and replaced immediately following treatment. Structures should be ventilated during application and until treatment is dry.
7. **Application using foam generating equipment:** The emulsion may be converted to a foam and the foam used to control or prevent termite infestations.

Depending on circumstances, foam applications may be used alone or in combination with liquid emulsion applications. Applications may be made behind veneers, piers, chimney bases, into rubble foundations, into block voids or structural voids, under slabs, stoops, porches, or to the soil in crawl spaces, and other similar voids.

Foam and liquid application must be consistent with volume and active ingredient instructions in order to ensure proper application has been made. The volume and amount of active ingredient are essential to an effective treatment. At least 50 to 75% of the labeled liquid emulsion volume

16/20

of product must be applied, with the remaining percent delivered to appropriate areas using foam application. Refer to the label and use recommendations of the foam manufacturer and the foaming equipment manufacturer for adjuvant rates to produce the needed expansion ratio with this product.

Foam applications are generally a good supplement to liquid treatments in difficult areas, but may be used alone in difficult spots.

The following provides the amount of Equity required for a given area and volume range of the prefoamed termiticide dilution necessary for application of the product.

For a 0.5% rate, apply 10 2/3 fluid ounces of Equity per 10 linear feet using no less than 2 gallons, or more than 8 gallons, of prefoamed dilution.

#### **Underground Utility Cable and Conduit (Non-residential)**

**Preventative Treatment For Use Only In Guam, Hawaii, and Other Pacific Islands:** Use a 1.0% to 2.0% dilution (See "Rate Determination Guidelines" and "Table 1" for dilution directions). After digging the trench, place approximately 6 inches of backfill or sand at the bottom and apply 2 gallons of the dilution per 10 linear feet. Allow to dry and place the cable on the backfill. Cover with an additional 6 inches of backfill or sand and apply another 2 gallons of emulsion per 10 linear feet. Finish filling trench with untreated soil.

Wherever cables emerge from the soil to enter poles, light frames, etc., treat the soil around the cable and pole or frame to establish a continuous 6 inch chemical barrier.

A continuous 6 inch chemical barrier must be established around the cable to insure protection from termite attack.

#### **Utility Poles and Fence Posts (Non-residential)**

**Preventative Treatment:** Use a 1.0% to 2.0% dilution (See "Rate Determination Guidelines" and "Table 1" for dilution directions). After pole or post hole has been dug, mix the dilution with the soil as it is being replaced to a depth of approximately 10 inches. Place pole or post on top of this layer. The remaining soil fill and termiticide dilution should be mixed while backfilling the hole. The treated soil zone around the post or pole should be approximately 6 inches wide. Soil for the base layer and backfill of each pole or post should be treated at a rate of 4 gallons of dilution per 10 cubic feet of soil.

**Remedial Treatment:** To control existing infestations or to prevent infestation of posts and poles already in place, use a 1.0% to 2.0% dilution. The termiticide dilution should be injected into termite galleries or channels in the wood. For maximum protection, injection sites should be at or below grade.

Posts or poles may also be treated by rodding down to the base of the structure. Rod holes should be placed approximately 3 inches away from the pole and about 6 inches apart. Inject approximately 12 fluid ounces of dilution per foot of depth into each rod hole.

It may be appropriate to use one or both treatment techniques depending upon the specific circumstances at the work site, e.g., soil type.



17/20

---

**General Pest Control - Perimeter Treatments  
(Industrial Plant Sites Only)**

---

**Directions for Perimeter Treatments**

Equity is intended to be mixed with water and applied outdoors with pressurized sprayers as a general surface spray.

**Applicator PPE for Perimeter Treatments**

- Wear eye protection when making overhead applications

**Precautions for Perimeter Treatments**

- Do not allow public access to treated surfaces until spray has dried.
- Keep out of fish pools and other bodies of water.
- Do not allow livestock to graze in treated areas.
- Do not feed treated grass cuttings (hay) or seed screenings to livestock, or use treated hay for livestock bedding.

**Treatment Sites**

When used in accordance to label directions Equity may be applied to and around outside surfaces of industrial plant sites. Permitted areas of use include but are not limited to:

decks	patios
driveways	refuse dumps
eaves	walkways
fences	walls
foundations	window and door frames
garages	

**Dosage Rates**

Applications of {0.03% to} 0.25% to 0.5% Equity can be made depending on pest species and method of application. See "Application Methods" for additional information.

**Mixing Directions**

{To make a 0.03% water based spray, add 1 2/3 fl oz Equity per 10 gallons of spray.} To make a 0.5% water based spray add 2 2/3 fl oz Equity per each gallon of spray.

A stable emulsion of Equity can be formed by first adding approximately one-half the water to the spray tank followed by adding the proper amount of Equity. Close the tank and agitate for 5 to 10 seconds. Add remaining water slowly to avoid excess foam.

**Tank Mixing**

Unless prohibited by a product's label, users, at their own discretion, can tank mix pesticides currently labeled for similar use patterns. It is always recommended that a small jar compatibility test using proper proportions of chemicals and water be run to check for physical compatibility prior to tank mixing. Do not tank mix this product with products containing dichlorvos (DDVP).

**Application Methods**

This product may be applied outdoors as a localized exterior surface treatment or soil applied perimeter treatment spray. Treat where pests are found or normally occur.

18/20

**Low Volume Directed Sprays**

Application of low volume, high concentration (about 0.5%) sprays can quickly reduce localized heavy pest infestations on outside surfaces. Use a low pressure system with a pinpoint or variable pattern nozzle, such as a 1 gallon hand pump sprayer, and apply the spray mixture to specific areas such as cracks and crevices along walkways, patios, windows and door frames or other areas where insects may congregate or can gain entrance to the structure.

**High Volume Broadcast Sprays**

Application of high volume, low concentration (0.03% - 0.12%) sprays, such as with power spraying equipment, can help prevent infestation of buildings by reducing pests in outdoor areas. Longer residual is achieved at the higher rates (about 0.12%). To make a 0.03% water based spray, mix 8 fl oz of Equity per 50 gallons. To make a 0.12% dilution, mix 32 fl oz of Equity per 50 gallons of water. This type of treatment provides more thorough coverage over large areas than low volume directed sprays. Treat by applying spray mixture directly to areas such as junctions of soil and structural walls and along the base of fences, and under eaves. To help prevent infestation of buildings, treat a band of soil 6 to 10 feet wide around and adjacent to buildings, also the building foundation to a height of 2 to 3 feet, where pests are active and may find entrance. Apply as a coarse spray at the rate of about 10 gallons spray mixture per 1000 square feet. Thoroughly and uniformly wet the treated area.

Small amounts of solution mixed at a 0.5% termiticide rate remaining in the spray tank can be diluted as indicated in the following table and used to treat outside surfaces or perimeter areas:

Concentration of Equity Dilution	Amount of water to Add to Each Gallon of Equity Dilution to Provide:		
	{0.03% Spray}	0.12% Spray	0.25% Spray
0.5%	{15.7 gallons}	3.2 gallons	1 gallon

**Pests Controlled by Perimeter Treatments of Equity**

- |                      |                           |
|----------------------|---------------------------|
| Ants                 | Elm leaf beetles (adults) |
| Bees                 | Fire ants (1)             |
| Beetles              | Fleas                     |
| Boxelder bugs        | Flies                     |
| (or other true bugs) | Hornets                   |
| Carpenter ants       | Millipedes                |
| Centipedes           | Mosquitoes                |
| Clover mites         | Pillbugs                  |
| Cockroaches          | Scorpions (2)             |
| (American)           | Sowbugs                   |
| (Asian)              | Spiders                   |
| (Brownbanded)        | Springtails               |
| (German)             | Ticks                     |
| (Oriental)           | Wasps                     |
| (Smokybrown)         | Yellowjackets and other   |
| Crickets             | outdoor insects           |
| Earwigs              |                           |

Numbers in parentheses (-) refer to "Specific Use Directions for Perimeter Treatments".

**Specific Use Directions for Perimeter Treatments:**

1. **Fire ant mounds** may be controlled by applying Equity as a drench. Dilute 2 fl oz per 4 gallons of water. Gently sprinkle 1 to 2 gallons of the diluted insecticide over the surface of each mound and surrounding areas to a 2 foot diameter. For best results, apply in cool weather, 65 to 80°F, or in early morning or late evening hours. Treat new mounds as they appear. Pressurized sprays may disturb the ants and cause migration, reducing product effectiveness.

19/20

2. **Scorpions** may be controlled by removing accumulations of lumber, and other materials serving as harborage sites. Before stacking lumber or other materials, apply Equity as a localized spray to surfaces immediately below such materials.

**Non-residential Turfgrass Areas  
(Including Golf Courses, Road Medians, and Industrial Plant Sites)**

Use Equity to control the pests listed in the following table by application at the recommended dosages. Dilute Equity in water and apply using suitable application equipment. For best results, turf should be moist at time of treatment.

Restriction: The maximum application rate is 2 qt (1 lb a.i.)/acre.

Pest	Amount of Equity per	
	1000 sq. ft.	Acre
Ants	1 1/2 fl oz	2 qt
Amyworms (Such as: Beet, Fall, Yellowstriped)		
Centipedes		
Chiggers (1)		
Chinch bugs		
Crickets		
Cutworms		
Deer ticks (2)		
Earwigs		
European crane fly larvae		
Fiery skipper		
Fire ants (foraging workers)		
Fire ants (mounds) (3)		
Fleas		
Billbug adults (Such as: Bluegrass, Denver, Hunting) (6)	1 1/2 fl oz	2 qt

Numbers in parentheses (-) refer to "Specific Use Directions".

**Specific Use Directions:**

1. Use Equity for area control of **ticks** and **chiggers** infesting golf courses, road medians, and industrial plant sites where these pests are present and create a nuisance or a possible public health problem. Do not allow public use of treated areas during application or until spray has dried. Apply Equity insecticide in water at the rate of 1 pint per acre (1/3 fl oz per 1000 sq. ft.) using a hydraulic sprayer, mist applicator, backpack sprayer, or other suitable hand or power operated spray equipment.
2. For control of **deer ticks** apply Equity in water at the rate of 2 quarts per acre or 1 1/2 fl oz per 1000 square feet. Treat low underbrush, turf, grassy areas, weeds, and ground surface and debris, using enough spray volume to obtain thorough coverage.
3. For individual **fire ant mounds** apply Equity as a drench. Dilute 2 fl oz per 4 gallons of water. Gently sprinkle 1 to 2 gallons of the diluted insecticide over the surface of each mound and surrounding areas to a 2 foot diameter. For best results, apply in cool weather, 65-80°F, or in early morning or late evening hours. Treat new mounds as they appear. Pressurized sprays may disturb the ants and cause migration, reducing product effectiveness.
4. **Mosquitoes** coming to rest on areas treated for control of turf pests will be controlled for varying periods of time after treatment depending on exposure of treated areas to weathering conditions.
5. For **sod webworms**, watering or mowing of the treated area should be delayed for 12 to 24 hours after treatment.
6. For **billbugs**, spray early in the season, just prior to or coinciding with first appearance of adults, as recommended by your local Agricultural Extension Service Specialist.

---

**Warranty Disclaimer**

---

Dow AgroSciences warrants that this product conforms to the chemical description on the label and is reasonably fit for the purposes stated on the label when used in strict accordance with the directions, subject to the inherent risks set forth below. Dow AgroSciences MAKES NO OTHER EXPRESS OR IMPLIED WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE OR ANY OTHER EXPRESS OR IMPLIED WARRANTY.

---

### **Inherent Risks of Use**

---

It is impossible to eliminate all risks associated with use of this product. Plant injury, lack of performance, or other unintended consequences may result because of such factors as use of the product contrary to label instructions (including conditions noted on the label, such as unfavorable temperature, soil conditions, etc.), abnormal conditions (such as excessive rainfall, drought, tornadoes, hurricanes), presence of other materials, the manner of application, or other factors, all of which are beyond the control of Dow AgroSciences or the seller. All such risks shall be assumed by buyer.

---

### **Limitation of Remedies**

---

The exclusive remedy for losses or damages resulting from this product (including claims based on contract, negligence, strict liability, or other legal theories), shall be limited to, at Dow AgroSciences' election, one of the following:

1. Refund of purchase price paid by buyer or user for product bought, or
2. Replacement of amount of product used

Dow AgroSciences shall not be liable for losses or damages resulting from handling or use of this product unless Dow AgroSciences is promptly notified of such loss or damage in writing. In no case shall Dow AgroSciences be liable for consequential or incidental damages or losses.

The terms of the "Warranty Disclaimer" above and this "Limitation of Remedies" cannot be varied by any written or verbal statements or agreements. No employee or sales agent of Dow AgroSciences or the seller is authorized to vary or exceed the terms of the "Warranty Disclaimer" or this "Limitation of Remedies" in any manner.

\*Trademark of Dow AgroSciences LLC  
EPA-Accepted:   /  /