CAUTION: Keep out of reach of children. Read caution and antidote statement on back panel.

NET CONTENTS — 1 QUART

Manufactured by CENOL CO., INC., CHICAGO, ILL. 60651

Mania and Rhododendron—Lace Bugs	1 pt/38 gal. water	Make application [illegible] Repeat in 2 or 3 weeks if necessary.
Oak—Thrips	1 pt/38 gal. water	Make application to tree when insects are present.

Apply sprays until runoff appears on above plants.

HOUSEHOLD AREA & INSECT PESTS	CONCENTRATION	DIRECTIONS
Inside Home—Ants	8 oz 1 gal. water	Thoroughly spray or paint on trails and areas around door sills and window frames, where ants may enter. Treat opening around water pipes, heat ducts, electrical outlets and baseboards where ants may come into rooms from wall spaces and partitions Repeat applications as necessary.
Carpet Beetles	8 oz. 1 gal. water	Thoroughly spray or paint infested areas of carpets localized areas of floors and baseboard, shelves of closets Repeat application as necessary
Centipedes and Spiders	8 oz/1 gal. water	Thoroughly spray or paint infested baseboards, corners, pipes, storage localities and other infested areas in basements. Repeat application as necessary to maintain effective control.
Crickets	8 oz/1 gal. water	Thoroughly spray or paint baseboards, floors of closets, storage places and other hiding places. Repeat application as necessary.
Roaches and Waterbugs	8 oz/1 gal. water	Thoroughly spray or paint infested cracks and other hiding places and of adjacent exposed surfaces where roaches will crawl when they come out of hiding. Repeat application as necessary.
Silverfish	8 oz 1 gal. water	Thoroughly spray or paint baseboards, areas behind shelving, bookcases, and storage areas.
TERMITE CONTROL In Buildings—Termites	1 qt/10 gal. water	*Apply emulsion as follows* (1) Slab-Type Construction (A)—Apply 1 gallon per 10 sq. ft. as an overall pre-construction treatment under the slab and under attached porches. (B)—Apply 2 gallons per 5 lineal feet to critical areas under the slab as pre-construction treatment, such as along the inside of foundation walls and around utility entrances and interior partition foundation walls. C—Apply 2 gallons per 5 lineal feet along the outside of the foundation using a trench to the depth of the foundation. (2) Crawl-Space Houses and Homes With Basement. (A)—Apply 2 gallons per 5 lineal feet as a trenching application to critical areas under the house, such as along the inside of foundation walls and around piers and utility entrances. If trench is deeper than 15-18 inches, apply 4 gallons per 5 lineal feet. (B)—Apply 2 gallons per 5 lineal feet in a trench along the outside of foundation walls, including entrance platforms and porches where the foundation is not more than 15-18 inches deep. If over 15-18 inches deep but not over 30 inches deep, apply 4 gallons per 5 lineal feet of trench. (C)—Apply 1 gallon per 10 sq ft of soil surface as a pre-construction treatment where the attached porches, entrance platforms, utility entrances, etc. have covering slab on fill of ground. A minimum of a 5 year control is obtained by the use of a 1% Chlordane emulsion in above application.

414-44