

OCTAGON PROCESS INC.
596 RIVER ROAD, EDGEWATER, NEW JERSEY 07020
OCTAGON FOOD PLANT SPRAY

FOR USE IN FOOD PROCESSING PLANTS, BOTTLING PLANTS, DAIRIES, SUPERMARKETS, RESTAURANTS, HOTELS, MOTELS, SCHOOLS AND HOSPITALS.

Kills on contact accessible or exposed stages of:

Flies	Roaches	Spiders	Bed Bugs
Fruit Flies	Ants	Wasps	Clover Mites
Mosquitoes	Crickets	Hornets	Cheese Mites
Silverfish	Gnats	Flying Moths	Scorpions

And these common STORED PRODUCTS pests:

Granary Weevil	Drugstore Beetle
Rice Weevil	Carpet Beetles
Spider Beetle	Meal Worms
Cigarette Beetle	Grain Mites

ACTIVE INGREDIENTS:

Pyrethrins	0.4%
*Piperonyl Butoxide, Technical	0.5%
N-octyl bicycloheptenedicarboximide	0.5%
Petroleum Distillate	98.6%

*Equivalent to 0.4% (butylcarbityl) (6-propylpiperonyl) ether and to 0.1% of related compounds

ACCEPTED

100% UNDER
 FUGA
 FOR
 ED
 TO
 and to 0.1% of related compounds

CAUTION
KEEP OUT OF REACH OF CHILDREN
DIRECTIONS FOR USE

AS A FOGGING SPRAY: Used according to directions, thorough fogging will control exposed stages of insects listed above. Use in food processing plants should be confined to time periods when the plant is not in operation. Foods should be removed or covered during treatment. All food processing surfaces should be covered during treatment or thoroughly cleaned before using. Remove pets, birds, and cover fish aquariums before spraying.

Close windows and doors and shut off ventilating systems. Apply with a good fogger or vaporizer adjusted to deliver a fine mist. In federally inspected meat and poultry processing plants, the fog particles should be in the aerosol range (no droplets over 50 microns in diameter and 80% less than 30 microns in diameter). Apply at the rate of 1 to 2 ounces per 1000 cubic feet of space. Direct spray toward the ceiling and into corners, thoroughly filling the area with vapor. Keep area closed for at least 15 minutes. Vacate the treated area and ventilate before reoccupying. Repeat treatment as necessary.

SURFACE SPRAY: This product may also be sprayed on surfaces to control Roaches, Silverfish, Crickets, Spiders, Clover Mites, Scorpions, Cheese Mites, Cheese Skippers, Spider Beetles. Use spray in a good machine adjusted to deliver a coarse, impet spray using approximately 1 gallon of material to each 750 square feet of surface. Spray infested areas thoroughly and direct the liquid behind baseboards, moldings, cabinets, shelves, sinks, door and window frames, and pipes, toward drains and dark corners, and into cracks, crevices, recesses and similar hiding places, under pallets and around stacks of packaged goods, hitting as many insects as possible directly with the spray. For best results, follow surface application with space spraying.

Against Ant Infestations: Treat shelves, cabinets, and storage areas. Spray ant trails, bait and thresholds and other places of entry, and treat nests liberally.

To Control Bedbugs effectively, apply liberally to top, ends, sides and bottom of mattresses, spraying thoroughly all tufts, seams and folds. Spray springs and frames, treating the liquid into all joints and lock joints. Treat walls, baseboards, moldings, floors, closets and behind furniture, picture frames, with particular attention to protected bedbug harbor and breeding places.

To Control Carpet Beetles effectively, apply to floor areas and baseboards. Spray liberally into cracks, crevices, and under carpets where insects may be found. Treat both the underside and top side of infested carpets. Spray inside of trunks, closets and infested areas of shelving.

AFTER

DANGER IF SWALLOWED. DO NOT DRAY NEAR FIRE OR OPEN FLAME. AVOID CONTAMINATION OF FEED AND FEEDSTUFFS.

FOR FURTHER INFORMATION, CONTACT THE MANUFACTURER OR THE DISTRIBUTOR. READ THE LABEL CAREFULLY. KEEP THIS LABEL ON THE CONTAINER. DO NOT REMOVE IT. IT IS A PART OF THE PRODUCT.

REGISTERED TRADEMARK OF OCTAGON PROCESS INC., EDGEWATER, N.J. 07020