DO IT YOURSELF -- SAL MONEY DIRECTIONS FOR USE

SUPER DRI KILL INSECTICIDE kills insects on contact through a physico-chemical action, it kills as long as this POW-DER IS PRESENT. When the insects walk or crawl through the powder, the powder causes the waxy skin to dissolve and it actually dries the insects to death, it is odorless, non-staining, it may be used in your home, apartments, restaurants, hotels, motels, offices, plants, stores, or other sites without damaging materials of any kind. It kills roaches on contact and protects against entrance of drywood termites into building. Once applied, powder leaves a long lasting protection that will kill new arrival insects months after the first application. SUPER DRI KILL INSECTI-CIDE - Kills Roaches (German Brown-Banded, Oriental), Fleas - Dogs and Cats.

NOTE: This container will cover 250 sq. ft, or more of floor space. In using this container as a dust gun, shake container, lift spout on cap. Now squeeze and apply into the out of the way places, shake as you apply beneath the refrigerator and behind, under and behind stove and heaters, under the sink, around pipe openings, in cracks and crevices where they may hide. Always apply powder in your household where it will not be disturbed by wet mopping, vacuuming or sweeping. Now take the cap off, sprinkle in the corners and recesses of cupboards, cabinets, drawers, shelves. Apply sufficient quantity for insects to make contact. NOW THIS IS IMPORTANT. If any excess powder is showing, take a small piece of cardboard and show the excess powder into the out of the way places where it will not be seen, and where it will do the most good.

A POINT TO REMEMBER LET SUPER DRI KILL INSECTICIDE REMAIN - DO NOT DISTURB AS LONG AS IT IS PRESENT - IT WILL KILL! KILL!

NOTE: Before applying in cupboards, cabinets, kitchen drawers, under the sink, remove dishes and utansits. Wipe all shelves with a cleaning agent, remove any material found, especially insect eggs.

BATHROOM -- LAUNDRY ROOM -- Apply at baseboards and any cracks and crevices around showers, tubs, pipe openings, drains, under and behind washers and dryers.

BEDROOMS — CLOSETS — HALLWAYS — LIVING ROOM — Check mattress and springs, apply in all cracks and crevices on bedstead. Check for hiding places and apply. FURNITURE — Turn solar and upholstery chairs to one side and apply powder to all holes and tears. Apply behind TV's, Stereos and other places where they may hide. Make your own survey and apply as needed. NOTE: There is a big advantage in using SUPER DRI KILL INSECTICIDE. As long as the powder is present you and your family are protected. Only monthly spot treatments will be necessary. STORAGE AREAS - Apply to all cracks and crevices, shelves, baseboards.

CARPETS - Always apply on carpet edges, DO NOT VACUUM - Heavy deposits, brush evenly.

FLEAS - DOGS AND CATS - Liberally apply powder to the animal, rubbing thoroughly to the skin. Beginning with the neck, ears, feet and legs, the base of the tail, the underbody, back and full length of the tail. Repeat as necessary. Surface of kennels or pet quarters should be dusted at the rate of one oz, per 50 square feet. Heavily infested areas, basements, and crawl spaces should be dusted at the rate of 16 oz, per 1,000 sq. ft. Repeat as necessary. Check other areas frequented by the animal. Make your own survey and apply as necessary.

NOTE: SUPER DRI KILL INSECTICIDE is a fluffy light weight powder. Once powder is applied correctly with sufficient coverage and not disturbed IN THE OUT OF WAY PLACES intestation can be eliminated. The secret is CORRECT AP-PLICATION — GOOD COVERAGE MONTHLY SPOT TREATMENTS IN TREATED AND UNTREATED AREAS.

DRY-WOOD TERMITES AND EXTREME INFESTATION OF INSECTS — Use an Electric or hand-operated rotary duster to distribute SUPER DRI KILL INSECTICIDE through the crawl hole into the attic. Rate of application recommended ONE POUND per 1,000 sq. ft. of floor area. All wood surfaces must be covered. All vents and louvers on the windward side to be closed. UNDER THE BUILDING — Same as above. Hand operated duster can be used in spot treatment.

NEW CONSTRUCTION — REMODELING — TERMITE REPAIRS — MINOR REPAIRS — To help prevent infestation of insects, apply powder between studding in lower part of outer walls, treat door casings, windows, floors, SUPER DRI KILL INSECTICIDE is an effective protection against future attacks in the powder treated areas.

PAINTING - EXTERIOR AND INTERIOR: Apply SUPER DRI KILL INSECTICIDE in all cracks and crevices, pipe and wire openings. Remove electrical receptacles, wall plates, switch plates. For extreme infestation, drill holes in plaster walls, wallboards, panels, anywhere it will do the most good. After treatment holes are closed by taping or best method. For large areas to dust we recommand more powder and the use of a Hand Operated Duster available at most Hardware Stores and Nurseries.

CAUTION: "Do not use in edible products areas of food processing plants, restaurants or other areas where food is commercially prepared or processed. Do not use in serving areas while food is exposed."

CAUTION: "NOT FOR OUTDOOR USE. Do not apply in areas where fish and wildlife are present."

DISTRIBUTED BY-SUPER KILL INSECTICIDE CO., P.O. BOX 461, SOUTH QATE, CALIF. 90280

SUPER DRI-KILL

INSECTICIDE Kills On Contact Of Powder

Use in and around Homes, Apartments, Restaurants, Hotels, Motels, Offices, Plants, Kennels, Stores, Food Processing Plants, etc.

GUARANTEED TO KILL ROACHES on contact

CONTROLS - PROTECTS - PREVENTS DRY WOOD TERMITE DAMAGE FLEAS DOGS AND CATS **CAUTION:**

KEEP OUT OF REACH OF CHILDREN AVOID INHALATION AVOID CONTAMINATION OF FOODSTUFFS

SEE REAR PANEL FOR ADDITIONAL PRECAUTIONS

ACTIVE INGREDIENTS:

Amorphous Silica Gel* — 95.0% Ammonium Fluosilicate — 2.0% . Inert Ingredients 3.0%

TOTAL — 100%

"DESTROY CONTAINER WHEN EMPTY" Developed in California

EPA REGISTRATION NUMBER 11257-2 EPA Est. No. 11257-CA-01

NET WT. 4 OZ. (113.4 GRAMS)

Amm Inert Ing In FU [-1 A. F i. €

NOTE: This settling will

container of fluffy powder occur during shipping and

r dust is sold by we d handling. Shake c

weight not ke container

t volume, : ir before u

using

0