

ACCEPTED

Apr-24-1967

550-112

**DIRECTIONS**

FOR CONTROL IN HOUSEHOLD of flying insects such as flies, mosquitoes, and gnats. Use 1 part MACLEAN'S 20% LINDANE IN OIL to 200 parts deodorized kerosene and apply with conventional mist type sprayer. For insects such as roaches, silverfish, spiders, and ants, use 1 part MACLEAN'S 20% LINDANE IN OIL to 50 parts deodorized kerosene and apply as a spray.

**FLIES, MOSQUITOES AND GNATS:** Close up infested area, spray, and leave closed for at least 10 minutes after treatment.

**ROACHES, SILVERFISH AND SPIDERS:** Spray on insects directly when possible, and spray into cracks and other hiding places. Repeat treatment as necessary.

**CLOTHES MOTHS:** Dilute MACLEAN'S 20% LINDANE IN OIL 1 to 200 parts (one tablespoonful per 3

5516-14  
REGISTERED  
COMMENTS.

**MACLEAN'S**

**20 % LINDANE IN OIL**

**INGREDIENTS**

**ACTIVE INGREDIENTS 100%**

Gamma Isomer of Benzene	
Hexachloride (from Lindane)	20.0%
Aromatic Petroleum Derivative Solvents	80.0%
(Contains 1.6 lbs. Lindane per Gallon)	

**CAUTION:**

**KEEP OUT OF REACH OF CHILDREN.**

May be absorbed through skin. Avoid breathing spray mist. Avoid contact with skin. In case of contact, wash immediately with soap and water. Harmful if swallowed. Do not use on household pets or humans. Avoid contamination of feeds and foodstuffs. **DO NOT STORE NEAR HEAT OR OPEN FLAME.**

MACLEAN'S 20% LINDANE IN OIL is a liquid formulation which can be diluted with oil base carriers and is adaptable to use in conventional mist sprayers.

MADE BY

**NEIL A. MACLEAN CO. INC.**

1536 Industrial Way, Belmont (S.F. Area), Calif.

**PRESNO**

**EL MONTE (L.A. Area)**

10-66

USDA Reg. No. 5316-14

quarts) with deodorized kerosene. Apply lightly but completely to infested areas on clothing and bedding. Materials being prepared for immediate storage may be sprayed with a 1 to 40 dilution, but such articles must be dry cleaned before use. Use a 1 to 40 dilution to spray closets, trunks, and other storage containers. Spray thoroughly and repeat monthly or as necessary.

**BEDBUGS:** Dilute one part MACLEAN'S 20% LINDANE IN OIL 1 to 200 parts (one tablespoonful per 3 quarts) with deodorized kerosene to make a 0.1% solution. Use this to spray thoroughly beds and mattresses, all cracks and hiding places about the bedroom, around baseboards, walls and floors. Repeat treatment as necessary.

Seller makes no warranty of any kind, express or implied, concerning the use of this product. Buyer assumes all risk of use or handling, whether in accordance with directions or not.

**NET CONTENTS**



550-112

TRANSFERRED FROM

~~5316-14~~ 5316-14