



UNITED STATES ENVIRONMENTAL PROTECTION AGENCY
WASHINGTON, D.C. 20460

OFFICE OF
PESTICIDES AND TOXIC SUBSTANCES

JUL 25 1991

Lisa R. Tartaglio
Sprayon Products
Division of the Sherwin-Williams Company
26300 Fargo Avenue
Bedford Heights, Ohio 44146

Dear Ms. Tartaglio:

Subject: Alternate formulation
862 Industrial Insecticide Spray
EPA. Reg. No. 10900-49
Submission: July 2, 1991

The labeling referred to above, submitted in connection with registration under the Federal Insecticide, Fungicide, and Rodenticide Act, as amended, is acceptable.

The alternate formulation for subject product is acceptable.

Sincerely,

A handwritten signature in dark ink, appearing to read "Rfm".

Richard F. Mountfort
Product Manager 10
Insecticide-Rodenticide Branch
Registration Division (H7505C)

BEST AVAILABLE COPY



00862 Industrial
Insecticide Spray

00862 provides rapid control of Houseflies, Mosquitoes, Small Flying Moths (Millers), Gnats, Wasps, and other pests of Roaches, Ants, Water Bugs, Silverfish, Flour Beetles, Weevils, Grain Mites, and Spiders. In hospitals, patients should be removed from room prior to treatment. Room should be ventilated two hours after spraying. Do not return patients to room until after ventilation.

Directions For Use

It is a violation of Federal law to use this product in a manner inconsistent with the labeling. **SHARE BEFORE USING AND AT INTERVALS DURING PROLONGED USE.** Hold container upright with nozzle away from you. Press button and spray as directed. To avoid possible staining of fabrics or surfaces, do not spray at close range.

Houseflies, Mosquitoes, Gnats, Wasps, and Small Flying Moths (Millers): Close all doors and windows and spray. Sprinkle the rate of 1/2 ounce per 1000 cubic feet. Direct spray to all parts of the room, especially windows and other light sources which attract these insects. Keep nozzle in room for 10 to 15 minutes after treatment. Repeat treatment as necessary.

Roaches, Waterbugs, Silverfish, Crickets, Spiders, Centipedes and Sow Bugs: Spray into hiding places such as cracks and crevices behind sinks, cabinets, along baseboards and floors around drains and plumbing, hitting insects with spray whenever possible. Repeat treatment as necessary.

Ants: Spray trails, nests and points of entry. Spray in ants where possible. Repeat as necessary.

Indian Meal Moths and Angoumois Grain Moths: Close doors and windows. Direct spray into all parts of room especially around stored food product containers, barrels and darkened areas. Spray 7 to 10 seconds for each 1000 cubic feet of space. Keep area closed for 15 minutes following treatment. Repeat application weekly or as needed.

Carpet Beetles: Spray directly on beetles, baseboards, floor shelves and carpets. Repeat as necessary.

Confused Flour Beetles, Saw-toothed Grain Beetles, Granary Weevils, Rice Weevils, Red Flour Beetles, Grain Mites: Spray into cracks and crevices, processing and handling equipment, around barrels or containers and other areas where these insects tend to congregate. Spray 30 seconds for each 100 square feet of surface. Keep area closed for 45 minutes to 1 hour after treatment. Repeat applications as necessary.

Lice: Spray on garments, bedding, mattresses, furniture, floors, carpeting and matinate surfaces. First spray an inconspicuous area to test for possible staining or discoloration. Inspect after drying; then proceed to spray entire area to be treated. Hold container upright with nozzle away from you. Press button and spray. Surface to be treated from a distance of 10 inches. Spray each square foot for 3 seconds. Directing spray into all infested surfaces until moist.

For Bedding: Make sure spray is directed to corners of bed sheets and blankets as well as inside and outside of pillow cases. In the case of garments and headgear, close attention should be given to seams, cuffs, collars and creases. After treatment, bedding and all garments must be either laundered in hot water or dry cleaned as required.


For Mattresses, Furniture and Carpeting: Direct spray into all folds, cracks, seams and crevices of infested area until moist. Allow all treated surfaces to dry completely before use.

NOT FOR USE ON HUMANS

Bedbugs: Spray mattresses, particularly around tufts and seams. Take beds apart and spray fully, under, in creases, baseboards, mudsaps and frames. Repeat treatment as necessary.

Fleas: Spray sleeping quarters, bedding, floor and furniture where pets are kept. Replace pet's old bedding. Repeat as necessary. Use only a recommended pet spray on pets.

To use entire contents: Hold spray head stationary and rotate can until material sprays as shown.



STORAGE AND DISPOSAL

Disposal: Do Not Reuse Empty Container. Wrap and Put in Trash Collection.

Storage: Store in a Cool Dry Place. Keep Container Closed.

Important Note: Buyer assumes all risks of use, storage or handling of this material not in strict accordance with directions given herewith.



For Professional and Industrial Use
SPRAYON PRODUCTS
Industrial Supply

Division of The Sherwin Williams Company
Bedford Heights, OH 44146 • Anaheim, CA 92807



00862

-862

Industrial Insecticide Spray

PYRENONE* Insecticide

Industrial Strength — Low Dosage Required

For Use in Schools, Hospitals, Institutions, Hotels, Dairies, Supermarkets, Restaurants, Drive-ins, Motels, Drugstores, and Animal Quarters.

ACTIVE INGREDIENTS:

Pyrethrins	0.40%
* Piperonyl Butoxide, Technical	2.00%
INERT INGREDIENTS:	97.60%
	100.00%

* Equivalent to 1.6% (Butylcarbyl) (6-propylpyrethryl) ether and 0.4% related compounds.

PYRENONE — Registered trademark of Fairfield American Corp.

EPA Reg. No. 10900-49

EPA Est. No. 10900-OH-1



KEEP OUT OF REACH OF CHILDREN
CAUTION
HARMFUL IF SWALLOWED OR INHALED.
AVOID CONTACT WITH SKIN.
See side panel for additional precautionary and practical treatment statements.

20 oz • 566 g net wt.

BEST AVAILABLE COPY

*70

1X A00642 OH-18

001147-5 2-511 The Sherwin Williams Co

AC
with
In EP

Under
Fungi
as a
reg