PM- 32

Reg # 57425-3 UNITED STATES ENVIRONMENTAL PROTECTION AGENCY

MAY 1 1 1995

Olivia D. Laird, Agent for Deatrick & Associates, Inc. 1013 East Taylor Run Parkway Alexandria, VA 22302

Hypochlor 10 x 70g Tablets for Klorman Chlorinator Subject: EPA Registration No. 57425-3 Your Amendment Dated February 3, 1995

Dear Ms. Laird:

)

)

This is in response to your re-submitted product labeling revised to include directions for use in emergency care areas.

The labeling referred to above, submitted in connection with registration under the Federal Insecticide, Fungicide, and Rodenticide Act, as amended, is acceptable subject to the comments listed below. A stamped copy is enclosed for your records. Five copies of the finished labeling must be submitted before the product is released for shipment bearing the amended labeling.

The use directions for "Bacterial Control in Sugar 1. Refineries" have been lined out in the enclosed stamped labeling copy. This use was not supported for reregistration.

- In the directions "For Use In Emergency Care Areas": 2.
  - Where it says, "Apply for 2 minutes," change "2" to (a) "10".
  - Revise the sentence, "Remove gross filth or heavy (b) soil by thorough cleaning of surfaces prior to application," to read, "Thoroughly clean all surfaces prior to application." (Thorough cleaning is to be required regardless of whether heavy deposits are present.)
  - Revise the disclaimer paragraph, "This product is (C) not to be used...," as indicated by the handwritten revisions in the enclosed stamped labeling copy.

CONCURRENCES										
SYMBOL										
SURNAME							* * * ** ** * * * * * * * * * * * * *	•••••		
DATE								,		
EPA Form 1320-1A (1/90)			Printed on Recycled Paper					OFFICIAL FILE COPY		

on Recyclea Pape

U S GPO 1994 522-503/82085 10818

2918

3. On the front panel, in the "If Swallowed" instructions in the First Aid section, expand the last sentence to read, "Call a physician immediately."

If you have any questions about these comments, please call Wallace Powell at (703) 305-6938.

Sincerely,

Ruth G. Douglas Product Manager (32) Antimicrobial Program Branch Registration Division (7505C)

Enclosure

;

)

Hipochlor 10 x 70 g TABLETS FOR

KLORMAN™ CHLORINATOR.

1 1 YAM

# KEEP OUT OF REACH OF CHILDREN

# DANGER.

# CONTAMINATION MAY CAUSE FIRE MIX ONLY INTO WATER SEE PRECAUTIONARY STATEMENT ON BACK PANEL.

ACTIVE INGREDIENT:		
Calcium Hypochlorite	68	S
INERT INGREDIENTS	·32	ያ
TOTAL	100	£

AVAILABLE CHLORINE							
EPA REG.	NO.	57425-3					
EPA EST	NO	57425 - SA -002					

# FIRST AID (PRACTICAL TREATMENT)

1

)

If on skin: Brush off excess chemical and flush skin with cold water for at least 15 minutes. If irritation persists, get medical attention.

If inhaled: Remove person to fresh air. Get immediate medical attention.

If swallowed: Drink large quantities of water. Do not induce vomiting. Call a physician. immediately.

If in eyes: Flush eyes with water for at least 15 minutes. Call a physician immediately.

Control Chemical D/b/a Deatrick and Associates 3345A Wakefield Street South Ar/Ington VA 22206

1

Nett weight: 1 lb 5 oz (10 x 70 gram tablets)

# PRECAUTIONARY STATEMENTS:

۰.

)

HAZARDS TO HUMANS AND DOMESTIC ANIMALS: DANGER. Highly corrosive. Causes skin and eye damage. May be fatal if swallowed. Do not get in eyes, or skin or on clothing. Do not handle with bare hands. Wear goggles or face shield and use rubber gloves and only thoroughly clean dry utensils when handling. Irritating to nose and throat. Avoid breathing dust and fumes. Remove and wash contaminated clothing before reuse.


CHEMICAL HAZARDS: DANGER. Strong oxidizing agent. Mix only into water. Contamination may start a chemical reaction with generation of heat, liberation of hazardous gases, and possible fire and explosion. Avoid any contact with flame or burning material, such as a lighted cigarette. Do not contaminate with moisture, garbage, dirt, chemicals including other pool chemicals, pool chlorination compounds, household products, cyanuric acid pool stabilizers., soap products, paint products, solvents, acids, vinegar, beverages, oils, pine oil, dirty rags or any other foreign matter.

EMERGENCY HANDLING: in case of contamination or decomposition, if possible, isolate container in open and well - ventilated area. Flood with large volumes of water. Dispose of contaminated material in an approved landfill area.

ENVIRONMENTAL HAZARD: This pesticide is toxic to fish and aquatic organisms. Do not discharge effluent containing this product into lakes, ponds, streams, estuaries, oceans or public waters unless this product is specifically identified and addressed in and NPDES permit. Do not discharge effluent containing this product to sewer systems without previously notifying the sewage treatment plant authority. For guidance contact your State Water Board or Regional Office of the EPA.

# STORAGE AND DISPOSAL

Keep this product dry in a tightly closed container when not in use. Store in a cool, dry, well ventilated area away from heat or open flame. In case off decomposition isolate container (if possible) and flood area with large amounts of water to dissolve all materials before discarding this container. Do not reuse empty container but place in trash collection. Do not contaminate food or feed by storage or disposal or cleaning of equipment.



It is a violation of federal law to use this product in a management inconsistent with its labeling.

Keep this product dry in a tightly closed contained, when not in use. Store in a cool, dry, well ventilated area away from heat or open flame. In case of decomposition, isolate container (if possible) and flood area with large amounts of water to dissolve all material tefore discarding this container. Do not reuse empty container but place in trash collection. Do not contaminate food or feed by storage, disposal, or cleaning of equipment.

### SWIMMING POOL WATER DISINFECTION

}

}

For a new pool or spring start-up, superchlorinate with 10 to 20 oz. of product for each 10,000 gallons of water to yield 5 to 10 ppm available chlorine by weight. Check the level of available chlorine with a test kit. Adjust and maintain pool water pH to between 7.2 to 7.6. Adjust and maintain the alkalinity of the pool to between 50 to 100 ppm.

To maintain the pool, add manually or by a feeder device 2 oz. of this product for each 10,000 gallons of water to yield an available chlorine residual between 0.6 to 1.0 ppm by weight. Stabilized pools should maintain a residual of 1.0 to 1.5 ppm available chlorine. Test the pH, available chlorine residual and alkalinity of the water frequently with appropriate test kits. Frequency of water treatment will depend upon temperature and number of swimmers.

Every 7 days, or as necessary, superchlorinate the pool with 10 to 20 oz. of product for each 10,000 gallons of water to yield 5 to 10 ppm available chlorine by weight. Check the level of available chlorine with a test kit. Do not reenter pool until the chlorine residual is between 1.0 to 3.0 ppm.

At the end of the swimming pool season or when water is to be drained from the pool, chlorine must be allowed to dissipate from treated pool water before discharge. Do not chlorinate the pool within 24 hours prior to discharge.

WINTERIZING POOLS - While water is still clear & clean, apply 0.6 oz. of product per 1000 gallons, while filter is running, to obtain a 3 ppm available chlorine residual, as detemined by a suitable test kit. Cover pool, prepare heater, filter and heater components for winter by following manufacturers' instructions.

SPAS, HOT-TUBS, IMMERSION TANKS, ETC.

SPAS/HOT-TUBS - Apply 0.5 oz. of product per 500 gallons of water to obtain a free available chlorine concentration of 5 ppm, as determined by a suitable chlorine test kit. Adjust and maintain pool water pH to between 7.2 and 7.8. Some oils, lotions, fragrances, cleaners, etc. may cause foaming or cloudy water as well as reduce the efficiency of the product.

To maintain the water, apply 0.5 oz. of product per 500 gallons of water, over the surface to maintain a chlorine concentration of 5 ppm.

5 9 18

After each use, shock treat with 1.5 oz. of this product per 500 gallons of water to control odor and algae.

During extended periods of disuse, add 1.5 oz. of product daily per 500 gallons of water to maintain a 3 ppm chlorine concentration.

HUBBARD AND IMMERSION TANKS - Add 0.5 oz. of this product per 100 gallons of water before patient use to obtain a chlorine residual of 25 ppm, as determined by a suitable test kit. Adjust and maintain the water pH to between 7.2 and 7.6. After each use drain the tank. Add 0.5 oz. to a bucket of water and circulate this solution

through the agitator of the tank for 15 minutes and then rinse out the solution. Clean tank thoroughly and dry with clean cloths.

HYDROTHERAPY TANKS - Add 1 oz. of this product per 1000 gallons of water to obtain a chlorine residual of 1 ppm, as determined by a suitable chlorine test kit. Pool should not be entered until the chlorine residual is below 3 ppm. Adjust and maintain the water pH to between 7.2 and 7.6. Operate pool filter continuously. Drain pool weekly, and clean before refilling.

#### SANITIZATION OF NONPOROUS FOOD CONTACT SURFACES

RINSE METHOD - A solution of 100 ppm available chlorine may be used in the sanitizing solution if a chlorine test kit is available. Solutions containing an initial concentration of 100 ppm available chlorine must be tested and adjusted periodically to insure that the available chlorine does not drop below 50 ppm. Prepare a 100 ppm sanitizing solution by thoroughly mixing 1 oz. of this product with 40 gallons of water. If no test kit is available, prepare a sanitizing solution by throughly mixing 1 oz. of this product with 20 gallons of water to provide approximately 200 ppm available chlorine by weight.

Clean equipment surfaces in the normal manner. Prior to use, rinse all surfaces thoroughly with the sanitizing solution, maintaining contact with the sanitizer for at least 2 minutes. If solution contains less than 50 ppm available chlorine, as determined by a suitable test kit, either discard the solution or

add sufficient product to reestablish a 200 ppm residual. Do not rinse equipment with water after treatment and do not soak equipment overnight. Sanitizers used in automated systems may be used for general cleaning but may not be re-used for sanitizing purposes.

IMMERSION METHOD - A solution of 100 ppm available chlorine may be used in the sanitizing solution if a chlorine test kit is available. Solutions containing an initial concentration of 100 ppm available chlorine must be tested and adjusted periodically to insure that the available chlorine does not drop below 50 ppm. Prepare a 100 ppm sanitizing solution by thoroughly mixing 1 oz. of this product with 40 gallons of water. If no test kit is available, prepare a sanitizing solution by throughly mixing 1 oz. of this product with 20 gallons of water to provide approximately 200 ppm available chlorine by weight.

Clear equipment in the normal manner. Prior to **provide the second secon** 

suitable test kit, either discard the solution or addition of the solution of a solution of the solution of th

1218

Sanitizers used in automated systems may be used for general leading but may not be re-used for sanitizing purposes.

FLOW/PRESSURE METHOD - Disassemble equipment and through clean after use. Assemble equipment in operating position prior to use. Thepare a volume of a 200 ppm available chlorine sanitizing solution equal to 110 % of volume capacity of the equipment by mixing the product in a ratio of 1 oz. product with 20 gallons of water. Pump solution through the system until full flow is obtained at all extremities, the system is completely filled with the sanitizer and all air is removed from the system. Close drain valves and hold under pressure for at least 2 minutes to, insure contact with all internal surfaces. Remove some cleaning solution from drain valve and test with a chlorine test kit. Repeat entire cleaning/sanitizing process if effluent contains less than 50 ppm available chlorine. Rinse system with potable water prior to use.

CLEAN-IN-PLACE METHOD - Throughly clean equipment after use. Prepare a volume of a 200 ppm available chlorine sanitizing solution equal to 110 % of volume capacity of the equipment by mixing the product in a ratio of 1 oz. product with 20 gallons of water. Pump solution through the system until full flow is obtained at all extremities, the system is completely filled with the sanitizer and all air is removed from the system. Close drain valves and hold under pressure for at least 10 minutes to insure contact with all internal surfaces. Remove some cleaning solution from drain valve and test with a chlorine test kit. Repeat entire cleaning/sanitizing process if effluent contains less than 50 ppm available chlorine. Rinse system with potable water prior to use.

وجميع والله بعد برداد جري مسير والعدي والعدي والجوية مدودياد خراج بكاله ا

SPRAY/FOG METHOD - Preclean all surfaces after use. Use a 200 ppm available chlorine solution to control bacteria, mold or fungi and a 600 ppm solution to control bacteriophage. Prepare a 200 ppm sanitizing solution of sufficient size by throughly mixing the product in a ratio of 1 oz. product with 20 gallons of water. Prepare a 600 ppm solution by thoroughly mixing the product in a ratio of 3 oz. product with 20 gallons of water. Use spray or fogging equipment which can resist hypochlorite solutions. Always empty and rinse spray/fog equipment with potable water after use. Throughly spray or fog all sufaces until wet, allowing excess sanitizer to drain. Vacate area for at least 2 hours. Prior to using equipment, rinse all surfaces treated with a 600 ppm solution with a 200 ppm solution.

# SANITIZATION OF POPOUS FOOD CONTACT SURFACES

RINSE METHOD - Prepare a sanitizing solution by throughly mixing 3 cz. of this product with 20 gallons of water to provide approximately 600 ppm available chlorine by weight. Clean surfaces in the normal manner. Prior to use, rinse all surfaces thoroughly with the sanitizing solution, maintaining contact with the sanitizer for at least 2 minutes. Rinse equipment with water after treatment and do not soak equipment overnight.

IMMERSION METHOD - Prepare a sanitizing solution by throughly mixing, in an immersion tank, 3 oz. of this product with 20 gallons of water to provide approximately 600 ppm available chlorine by weight. Clean equipment in the

normal manner. Prior to use, immerse equipment in the sanitizing solution for at least 2 minutes and allow the sanitizer to drain. Rinse equipment with water after treatment.

l

SPRAY/FOG METHOD - Preclean all surfaces after use. Prepare a 600 ppm available chlorine sanitizing solution of sufficient size by throuoghly mixing the product in a ratio of 3 oz. product with 20 gallons of water. Use spray or fogging equipment which can resist hypochlorite solutions. Always empty and rinse spray/fog equipment with potable water after use. Throughly spray or fog all sufaces until wet, allowing excess sanitizer to drain. Vacate area for at least 2 hours. Prior to using equipment, rinse all surfaces with a 200 ppm available chlorine solution. Prepare a 200 ppm sanitizing solution by thoroughly mixing 1 oz. of this product with 20 gallons of water.

# SANITIZATION OF NONPOROUS NON-FOOD CONTACT SURFACES

RINSE METHOD - Prepare a sanitizing solution by throughly mixing 1 oz. of this product with 20 gallons of water to provide approximately 200 ppm available chlorine by weight. Clean equipment surfaces in the normal manner. Prior to use, rinse all surfaces thoroughly with the sanitizing solution, maintaining contact with the sanitizer for at least 2 minutes. Do not rinse equipment with water after treatment and do not soak equipment overnight.

IMMERSION METHOD - Prepare a sanitizing solution by throughly mixing, in an immersion tank, 1 oz. of this product with 20 gallons of water to provide approximately 200 ppm available chlorine by weight. Clean equipment in the normal manner. Prior to use, immerse equipment in the sanitizing solution for at least 2 minutes and allow the sanitizer to drain. Do not rinse equipment with water after treatment.

SPRAY/FOG METHOD - Preclean all surfaces after use. Prepare a 200 ppm available chlorine sanitizing solution of sufficient size by throughly mixing the product in a ratio of 1 oz. product with 20 gallons of water. Use spray or fogging equipment which can resist hypochlorite solutions. prior to using equipment, throughly spray or fog all sufaces until wet, allowing excess sanitizer to drain. Vacate area for at least 2 hours.

# DISINFECTION OF NONFOROUS NON-FOOD CONTACT SURFACES

RINSE METHOD - Prepare a disinfecting solution by throughly mixing 3 oz. of this product with 20 gallons of water to provide approximately 600 ppm available chlorine by weight. Clean equipment surfaces in the normal manner. Prior to use, rinse all surfaces thoroughly with the disinfecting solution, maintaining contact with the solution for at least 10 minutes. Do not rinse equipment with water after treatment and do not soak equipment overnight.

MAY I I WE

IMMERSION METHOD - Prepare a disinfecting solution by throughly mixing, in an immersion tank 3 oz. of this product with 20 gallons of water to provide approximately 6.0 ppm available chlorine by weight. Clean equipment in the normal manner. Prior to use, immerse equipment in the disinfecting solution for with water after treatment. The EPA Letter Deter

Z

# SANITIZATION OF POROUS NON-FOOD CONTACT SURFACES

RINSE METHOD - Prepare a sanitizing solution by throughly mixing 3 oz. o this product with 20 gallons of water to provide approximately 600 ppm available chlorine by weight. Clean surfaces in the normal manner. Prior to use, ri se all surfaces thoroughly with the sanitizing solution, maintaining contact with the sanitizer for at least 2 minutes. Do not rinse equipment with water atter treatment and do not soak equipment overnight.

ور والمحمد – م والرائد الد اليان او الحد عداد بد و ها عداد ما و عالمه و عالمه

IMMERSION METHOD - Prepare a sanitizing solution by throughly mixing, in an immersion tank, 3 oz. of this product with 20 gallons of water to provide approximately 600 ppm available chlorine by weight. Clean equipment in the normal manner. Prior to use, immerse equipment in the sanitizing solution for at least 2 minutes and allow the sanitizer to drain. Do not rinse equipment with water after treatment.

مر میکارد نوان است. از میرود مرکزه و چرن و چرو میکند<sup>و</sup> کر نوبی می مرکزه

}

SPRAY/FOG METHOD - After cleaning, sanitize non-food contact surfaces with 600 ppm available chlorine by throuoghly mixing the product in a ratio of 3 oz. of this product with 20 gallons of water. Use spray or fogging equipment which car resist hypochlorite solutions. Always empty and rinse spray/fog equipment with potable water after use. prior to using equipment, throughly spray or fog all sufaces until wet, allowing excess sanitizer to drain. Vacate area for at least 2 hours.

### SEWAGE & WASTEWATER EFFLUENT TREATMENT

The disinfection of sewage effluent must be evaluated by determining the total number of coliform bacteria and/or fecal coliform bacteria, as determined by the Most Probable Number (MPN) procedure, of the chlorinated effluent has been reduced to or below the maximum permited by the controlling regulatory jurisdiction.

On the average, satisfactroy disinfection of secondary wastewater effluent can be obtained when the chlorine residual is 0.5 ppm after 15 minutes contact. Although the chlorine residual is the critical critical factor in disinfection, the importance of correlating chlorine residual with bacterial kill must be emphasized. The MPN of the effluent, which is directly related to the water quality standards requirements, should be the final and primary standard and the chlorine residual should be considered an operating standard valid only to the extent verified by the coliform quality of the effluent.

The following are critical factors affecting wastewater disinfection.

1. Mixing: It is imperative the me product and the wastewater by instantaneously and complete product of assure reaction with every chemically active setuple and particulate component of the wastewater.

2. Contacting: Upon flash mixing dether that hrough the system must be maintained.

3. Dosage/Residual Control and to maintain a predetermined, desirable chlorine level. Secondary effluent should

10 9 18-

contain 0.2 to 1.0 ppm chlorine residual after a 15 to 30 minute contact time. A reasonable average of residual chlorine is 0.5 ppm after 15 minutes contact time.

### SEWAGE AND WASTEWATER TREATMENT

CERTINE SLIME CONTROL - Apply a 100 to 1000 ppm available chlorine solution at a bocavion which will allow complete mixing. Prepare this solution by mixing 2 to of this product with 100 gallons of water. Once control is evident, apply a 1 form available chlorine solution. Prepare this solution by mixing 0.3 oz. of this product with 100 gallons of water.

FILTER BEDS - SLIME CONTROL: Remove filter from service, drain to a depth of 1 ft above filter sand, and add 16.02. of product per 20 sq/ft evenly over the surface Wait 30 minutes before draining water to a level that is even with the top of the filter. Wait for 4 to 6 hours before completely draining and backwashing filter.

DISINFECTION OF DRINKING WATER (EMERGENCY/PUBLIC/INDIVIDUAL SYSTEMS)

PUBLIC SYSTEMS: Mix a ratio of 1 or. of this product to 6000 gallons of water. Begin feeding this solution with a hypochlorinator until a free available chlorine residual of at least 0.2 ppm and no more than 0.6 ppm is attained throughout the distribution system. Check water frequently with a chlorine test kit. Bacteriological sampling must be conducted at a frequency no less than that prescribed by the National Interim Primary Drinking Water Regulations. Contact your local Health Department for further details.

INDIVIDUAL SYSTEMS: - DUG WELLS Upon completion of the casing (lining) wash the interior of the casing (lining) with a 100 ppm available chlorine solution using a stiff brush. This solution can be made by throughly mixing 1 oz. of this product into 40 gallons of water. After covering the well, pour the sanitizing solution into the well through both the pipesleeve opening and the pipeline. Wash the exterior of the pump cylinder also with the sanitizing solution. Start pump and pump water until strong odor of chlorine in water is noted. Stop pump and wait at least 24 hours. After 24 hours flush well until ( all traces of chlorine have been removed from the water. Contact your local Health Department for further details.

INDIVIDUAL WATER SYSTEMS: DRILLED, DRIVEN & BORED WELLS - Run pump until water water is as free from turbity as possible. Pour a 100 ppm available chlorine sanitizing solution into the well. This solution can be made by throughly mixing 1 oz. of this product into 40 gallons of water. Add 5 to 10 gallons of clean, chlorinted water to the well in order to force the sainizer into the rock formation. Wash the exterior of pump cylinder with the sanitizer. Trop pipeline into well, start pump and pump water until strong odor of chlorine in water is noted. Stop pump and wait at least 24 hours. After 24 hours flush well until all traces of chlorine have been removed from the water. Deep wells with high water levels may necessitate the use of special methods for introduction of the sanitizer into the well. Consult your local Scalth Department for further details.

. INDIVIDUAL WATER SYSTEMS: FLOWING ARTESIAN WELLS Artesian wells generally ...20 not require disinfection. If analyses indicate persistant contamination, ...the well should be disinfected. Consult your local Health Department for further details.

EMERGENCY DISINFECTION - When boiling of water for 1 minute is not practical, water can be made potable by using this product. Prior to addition of the sanitizer, remove all suspended material by fistration or by allowing it to settle to the bottom. Decant the clarified, contaminated water to a clean container and add 1 grain of this product to 1 gallon of water. One grain approximately the size of the letter "O" in this sentence. Allow the water to stand for 30 minutes. Properly treaced water should have a solute chlorine odor, if not, repeat dosage and allow the water to stand with odition al 15 minutes. The treated water can then be made palatable by pouting between clean containers for several times.

# PUBLIC WATER SYSTEMS

RESERVOIRS - ALGAE CONTROL: Hypochlorinate, streams feeding the reserve feeding points should be selected on each stream at least 50 yards upstream from the points of entry into the reservoir.

- ) MAINS Thoroughly flush section to be sanitized by discharging from hydrants. Permit a water flow of at least 2.5 feet per minute to continue under pressure while injecting this product by means of a hypochlorinator. Stop water flow when a chlorine residual test of 50 ppm is obtained at the low pressure end of the new main section after a 24 hour retention time. When chlorination is completed, the system must be flushed free of all heavily chlorinated water.
- NEW TANKS, BASINS, ETC. Remove all physical soil from surfaces. Place 4 oz. of this product for each 5 cubic feet of working capacity (500 ppm available chlorine. Fill to working capacity and allow to stand for at least 4 hours. Drain and flush with potable water and return to surface.

NEW FILTER SAND - Apply 16 oz. of this product for each 150 to 200 cubic feet of sand. The action of the product dissolving as the water passes through the bed will aid in sanitizing the new sand.

NEW WELLS - Flush the casing with a 50 ppm available chlorine solution of water containing 1 oz. of this product for each 100 gallons of water. The solution should be pumped or fed by gravity into the well after thorough mixing with agitation. The well should stand for several hours or overnight under chlorination. It may then be pumped until a representative raw water sample is obtained. Bacterial examination of the water will indicate whether further treatment is necessary.

EXISTING EQUIPMENT - Remove equipment from service, thoroughly clean surfaces of all physical soil. Sanitize by placing 4 oz. of this product for each 5 cubic feet capacity (approximately 500 ppm available chlorine). Fill to working capacity and let stand at least 4 hours. Drain and place in service. If the previous treaument is not practical, surfaces may be sprayed with a solution containing 1 oz. of this product for each 5 gallons of water (approximately 1000 ppm available chlorine). After drying, flush with water and return to service.

#### EMERGENCY DISINFECTION AFTER FLOODS

WELLS - Thoroughly flush contaminated casing with a 500 ppm available chloring solution. Prepare this solution by mixing 1 oz. of this product with 10 gallous of water. Backwash the well to increase yield and reduce turbidity, adding sufficient

//

chlorinating solution to the backwash — produce a 10 ppm available chlorine residual, as determined by a chlorine test kit. After the turbididty has been reduced and the casing has been treated, add sufficient chlorinating solution to produce a 50 ppm available chlorine residual. Aggitate the well water for several hours and take a representative water sample. Retreat well if water samples are biologically unacceptable.

RESERVOIRS - In case of contamination by overflowing streams, establish hypochlorinating stations upstream of the reservior. Chlorinate the inlet water until the entire reservior obtains a 0.2 ppm available chlorine residual, as determined by a suitable chlorine test kit. In case of contamination from surface drainage, apply sufficient product directly to the reservior to obtain a 0.2 ppm available chlorine residual in all parts of the reservior.

الم محمد العام عن اليون الله المحمد اليون في ما في 10 (م. ش. العالي و. الي .

BASINS, TANKS, FLUMES, ETC. - Thoroughly clean all equipment, then apply 4 oz. of product per 5 cu. ft. of water to obtain 500 ppm available chlorine, as determined by a suitable test kit. After 24 hours drain, flush, and return to service. If the previous method is not suitable, spray or flush the equipment with a solution containing 1 oz. of this product for each 5 gallons of water (1000 pravailable chlorine). Allow to stand for 2 to 4 hours, flush and return to servit

FILTERS - When the sand filter needs replacement, apply 16 oz. of this product for each 150 to 200 cubic feet of sand. When the filter is severely contaminated, additional product should be distributed over the surface at the rate of 16 oz. per 20 sq. ft.. Water should stand at a depth of 1 foot above the surface of the filter bed for 4 to 24 hours. When filter beds can be backwashed of mud and silt, apply 16 oz. of this product per each 50 sq. ft., allowing the water to stand at a depth of 1 foot above the filter sand. After 30 minutes, drain water to the level of the filter. After 4 to 6 hours drain, and proceed with normal backwashing.

\_\_\_\_\_

DISTRIBUTION SYSTEM - Flush repaired or replaced section with water. Establish a hypochlorinating station and apply sufficient product until a consistent available chlorina residual offert least 10 ppm remains after a 24 hour retention time. Use a chlorine test kit is a

# $\eta$ emergency disinfection after fires

CROSS CONNECTIONS - Hypochlorination or gravity feed equipments and the set up near the intake of the untreated water supply. Apply sufficient product to give a chlorine residual of at least 0.1 to 0.2 ppm at the point where the untreated supply enters the regular distribution system. Use a chlorine test kit.

# EMERGENCY DISINFECTION AFTER DROUGHTS

SUPPLEMENTARY WATER SUPPLIES - Gravity or mechanical hypochlorite feeders should be set up on a supplementary line to dose the water to a minimum chlorine residual of 0.2 ppm after a 20 minute contact time. Use a chlorine test kit.

WATER SHIPPED IN BY TANKS, TANK CARS, TRUCKS, ETC. - Thoroughly clean all container and equipment. Spray a 500 ppm available chlorine solution and rinse with potable water after 5 minutes. This solution is made by mixing 1 oz. of this product for each 5 gallons of water. During the filling of the containers, dose with sufficient .andunts of this product to provide at least a 0.2 ppm chlorine residual. Use a .chlorine test kit.

# EMERGENCY DISINFECTION AFTER MAIN BREAKS

MAINS - Before assembly of the repaired section, flush out mud and soil. Permit a water flow of at least 2.5 feet per minute to continue under pressure while injecting this product by means of a hypochlorinator. Stop water flow when a chlorine residual test of 50 ppm is obtained at the low pressure end of the new main section after a 24 hour retention time. When chlorination is completed, the system must be flushed free of all heavily chlorinated water.

# COOLING TOWER/EVAPORATIVE CONDENSER WATER

}

)

SLUG FEED METHOD - Initial Dose: When system is noticably fouled, apply 10 to 20 oz. of this product per 10,000 gallons of water in the system to obtain from 5 to 10 ppm available chlorine. Repeat until control is achieved. Subsequent Dose: When microbial control is evident, add 2 oz. of this product per 10,000 gallons of water in the system daily, or as needed to maintain control and keep the chlorine residual at 1 ppm. Badly fouled systems must be cleaned befor treatment is begun.

INTERMITTENT FEED METHOD - Initial Dose: When system is noticably fouled, apply 10 to 20 oz. of this product per 10,000 gallons of water in the system to obtain 5 to 10 ppm available chlorine. Apply half (or 1/3, 1/4, or 1/5) of this intial dose when half (or 1/3, 1/4, or 1/5) of the water in the system has been lost by blowdown.

Subsequent Dose: When microbial control is evident, add 2 pz. of this product per 10,000 gallons of water in the system to obtain a 1 ppm residual. Apply half (or 1/3, 1/4, or 1/5) of this intial dose when half (or 1/3, 1/4, or 1/5) of the water in the system has been lost by blowdown. Badly fouled systems must be cleaned before treatment is begun.

CONTINUOUS FEED METHOD - Initial Dose: When system is noticably fouled, apply 10 to 20 oz. of this product per 10,000 gallons of water in the system to obtain 5 to 10 ppm available chlorine.

Subsequent Dose: Maintain this treatment level by starting a continuous feed of 1 oz. of this product per 3,000 gallons of water lost by blowdown to maintain a 1 ppm residual. Badly fouled systems must be cleaned before treatment is bequn.

BRIQUETTES OR TABLETS - Initially slug dose the system with 10 oz. of this product per 10,000 gallons of water in the system. Badly fouled systems must be cleaned before treatment is begun.

Subsequent Dose: When microbial control is evident, add 2 oz. of this product per 10,000 gallons of water in the systemodaily, or as needed to maintain control and keep the chlorine residuate for bem. Badly fouled systems must be cleaned before treatment is begun. The CONTRACT Data TO EPA Letter Data

MAY 1 , 1595

Under the Federal Insecticute, Under the Federal Insecticute, Functional, and Roter, Sinde Asta Functional, Col the FPA Rea emended under EPA Rea resistend

. . . . .

# LAUNDRY SANITIZERS

Household Laundry Sanitizers

IN SOAKING SUDS - Thoroughly mix 1 Tbs. of this product to 10 gallons of wash water to provide 200 ppm available chlorine. Wait 5 minutes, then add soap or detergent. Immerse laundry for at least 11 minutes prior starting the wash/rinse cycle.

IN WASHING SUDS - Thoroughly mix 1 Tbs. of this product to 10 gallons of wash

water containing clothes to provide 200 ppm available chlorine. Wait 5 minutes,

then adding soap or detergent and start the wash/rinse cycle.

# Commercial Laundry Sanitizers

Wet fabrics or clothes should be spun dry prior to sanitization. Thoroughly mix 1 oz. of this product with 20 gallons of water to yield 200 ppm available chlorine. Promptly after mixing the sanitizer, add the solution into the prewash prior to washing fabrics/clothes in the regular wash cycle with a good detergent. Test the level of available chlorine, if solution has been allowed to stand. Add more of this product if the the available chlorine level has dropped below 200 ppm.

### FARM PREMISES

Remove all animals, poultry, and feed from premises, vehicles, and enclosures. Remove all litter and manure from floors, walls and surfaces of barns, pens, stalls, chutes and other facilities occupied or transverse by animals or poultry. Empty all troughs, racks and other feeding and watering appliances. Throughly clean all sufaces with soap or detergent and rinse with water. To disinfect, saturate all surfaces with a solution of at least 1000 ppm available chlorine for a period of 10 minutes. A 1000 ppm solution can be made by thoroughly mixing 2 oz. of this product with 10 gallons of water. Immerse all halters, ropes and other types of equipment used in handling and restraining animals or poultry, as well as the cleaned forks, shovels and scrapers used for removing litter and manure. Ventilate buildings, cars, boats and other closed spaces. Do not house livestack or poultry or employ equipment until chlorine has been dissipated. All treated feed racks, mangers, troughs, automatic feeders, fountains and waterers must be rinsed with potable water before reuse.

#### PULP AND PAPER MILL PROCESS WATER SYSTEMS

SLUG FEED METHOD - Initial Dose: When system is noticably fouled, apply 10 to 20. pz. of this product per 10,000 gallons of water in the system to obtain from 5 to 10 pom available chlorine. Repeat until control is achieved.

Subsequent Doss: When microbial control is evident, add 2 oz. of this product per 10,000 gallons of water in the system daily, or as needed to maintain control and keep the chlorine residual at 1 ppm. Badly fouled systems must be cleaned before creatment is begun.

14

INTERMITTENT FEED METHOD - Initial Dose: When system is noticably fouled, apply 10 to 20 oz. of this product per 10,000 gallons of water in the system to obtain 5 to 10 ppm available chlorine. Apply half (or 1/3, 1/4, or 1/5) of this initial dose when half (or 1/3, 1/4, or 1/5) of the water in the system has been lost by blowdown.

Subsequent Dose: When microbial control is evident, add 2 oz. of this product per 10,000 gallons of water in the system to obtain a 1 ppm residual. Apply half (or 1/3, 1/4, or 1/5) of this intial dose when half (or 1/2) of or 1/5) of the water in the system has been lost by blowdown. Badly for the systems mus be cleared before treatment is begun.

CONTINUOUS FEED METHOD - Initial Dose: When system is noticably fouled to 10 to 20 oz. of this product per 10,000 gallons of water in the system to 10 obtain 5 to 10 ppm available chlorine.

Subsequent Dose: Maintain this treatment level by starting a contratious feed of 2 oz. of this product per 1,000 gallons of water lost by blowdown to maintain a 1 ppm residual. Badly fouled systems must be cleaned before treatment is begun.

BRIQUETTES OR TABLETS - Initially slug dose the system with 10 oz. of this product per 10,000 gallons of water in the system. Badly fouled systems must be cleaned before treatment is begun.

Subsequent Dose: When microbial control is evident, add 2 oz. of this product per 10,000 gallons of water in the system daily, or as needed to maintain control and keep the chlorine residual at 1 ppm. Badly fouled systems must be cleaned before treatment is begun.

### AGRICULTURAL USES

)

POST-HARVEST PROTECTION - Potatoes can be sanitized after cleaning and prior to storage by spraying with a sanitizing solution at a level of 1 gallon of sanitizing solution per tons of potatoes. Thoroughly mix 1 oz. of this product to 10 gallons of water to obtain 500 ppm available chlorine.

ر ویکون کشت م جبب به زمند زد و نصوی وی و و و پیچ و و و و و

Disinfect leafcutting bee cells and bee boards by immersion in a solution containing 1 ppm available chlorine for 3 minutes. Allow cells to drain for 2 minutes and dry for 4 to 5 hours or until no chlorine odor can be detected. This solution is made by thoroughly mix 1/4 Tsp. of this product to 200 gallons of water. The bee domicile is disinfected by spraying with a 0.1 ppm solution until all surfaces are thoroughly wet. Allow the domicile to dry until all chlorine odor has dissipated.

ملد برب هی ۵ الدن م <del>ن</del> ن و و مربع محمد مدر و <sub>ا</sub>مد ه د د د م

FOOD EGG SANITIZATION - Throughly clean all eggs. Thoroughly mix 1 oz. of this product with 20 gallons of warm water to produce a 200 ppm available chlorine solution. The sanitizer temperature should not exceed 130°F. Spray the warm sanitizer so that the eggs are thoroughly wetted. Allow the eggs to thoroughl dry before casing or breaking. Do not apply a potable water rinze. The edution should not be re-used to sanitize eggs.

FRUIT & VEGETABLE WASHING - Thoroughly clean all fruits and vegetables in a wash tank. Thoroughly mix 1 oz. of this product in 200 gallons of water to

ر ا

make a sanitizing solution of 25 ppm available chlorine. After draining the tank, submerge fruit or vegetables for 2 minutes in a second wash tank containing the recirculating sanitizing solution. Spray rinse vegatables with the sanitizing solution prior to packaging. Rinse fruit with potable water only prior to packaging.

SEEDS - To control bacterial spot (<u>Xanthomonas vesticatoris</u>) on Pimento seeds, initially remove moist seeds from ripe fruits. To control surface fungi and bacteria on Tomato seeds initially wash seeds. Immediately soak seeds in 39,000 ppm solution for 15 minutes with continuous aggitation. After treatment rinse seeds in potable water for 15 minutes. Dry seeds to normal moisture. The solution may be made by mixing 8 oz. of this product with 1 gallon of water.

MUSHROOMS - To control bacterial blotch (<u>Pseudomonas tolaasii</u>), use a 100 to 200 ppm solution prior to watering mushroom production surfaces. This solution may be made by mixing 0.2 to 0.4 oz. of this product with 10 gallons of water. First applicatio should begin when pins form, and thereafter, between breaks on a need basis dependin on the occurence of bacterial blotch. This product may be applied directly to pins to control small infection foci. Apply 1.5 to 2.0 oz. per square foot of growing 3

POST-HARVEST ROOTS - To control and reduce the spread of soft rot causing organisms in water and on sweet potatoes (<u>Ipomoea batatas</u>), spray or dip the potatoes with a 150 to 500 ppm solution for 2 to 5 minutes. Thoroughly mix 0.3 to 1.0 oz. of this product per 10 gallons of water to obtain this solution. Monitor the chlorine concentration and change the solution after one hour or as needed.

# AQUACULTURAL USES

FISH PONDS - Remove fish from ponds prior to treatment. Thoroughly mix 20 oz. of this product to 10,000 gallons of water to obtain 10 ppm available chlorine. Add more product to the water if the available chlorine level is below 1 ppm after 5 minutes. Return fish to pond after the available chlorine level reaches zero.

FISH POND EQUIPMENT - Thoroughly clean all equipment prior to treatment. Thoroughly mix 1 oz. of this product to 20 gallons of water to obtain 200 ppm available chlorine. Porous equipment should soak for one hour.

MAINE LOBSTER PONDS - Remove lobsters, seaweed etc. from ponds prior to treatment. Drain the pond. Thoroughly mix 1200 oz. of this product to 10,000 gallons of water to obtain at least 600 ppm available chlorine. Apply so that all barrows, gates, rock and dam are treated with product. Permit high tide to fill the pond and then close gates. Allow water to stand for 2 to 3 days until the available chlorine level reaches zero. Open gates and allow 2 tidal cycles to flush the pond before returning lobsters to pond.

CONDITIONING LIVE OYSTERS - Thoroughly mix 1 oz. of this product to 10,000 gallons of water at 50 to 70°F to obtain 0.5 ppm available chlorine. Expose oysters to this solution for a least 15 minutes, monitoring the available chlorine level so that to does not fall below 0.05 ppm. Repeat entire process if the available chlorine level drops below 0.05 ppm or the temperature falls below 50°F.

....

CONTROL OF SCAVENGERS IN FISH HATCHERY PONDS - Prepare a solution containing 200 ppm of available chlorine by mixing 0.5 oz. of product with 10 gallons of water, Pour into drained pond potholes. Repeat if necessary. Do not put desirable fish back into refilled ponds until chlorine residual has dropped to 0 ppm, as determined by a test kit.

# SANITIZATION OF DIALYSIS MACHINES

ł

)

Flush equipment thoroughly with water prior to using this product. Thoroughly mix 7 oz. of this product to 60 gallons of water to obtain at least 600 ppm available chlorine. Immediately use this product in the hemodialysate system allowing for a minimum contact time of 15 minutes at 20°F C. Drain system of the sanitizing solution and thoroughly rinse with water. Discard and DO NOT reuse the spent sanitizer. Rinsate must be monitored with a suitable test kit to insure that no available chlorine remains in the system.

This product is recommended for decontaminating single and multipatient hemodialysate systems. This product has been shown to be an effective disinfectant (virucide, fungicide, bactericide, pseudomonicide) when tested by AQAC and EPA test methods. This product may not totally eliminate all vegatative microorganisms in hemodialysate delivery systems due to their construction and/or assembly, but can be relied upon to reduce the number of microorganisms to acceptable levels when used as directed. This product should be used in a disinfectant program which includes bacteriologiocal monitoring of the hemodialysate delivery system. This product is NOT recommended for use in hemodialysate or reverse osmosis (RO) membranes.

Consult the guidelines for hemodialysate systems which are available the in EPA Letter Deter Hepititis Laboratories, CDC, Phoenix, AR 85021.

# TOILET BOWL SANITIZERS

[These products are marketed as individual packages for placement in the  $m_{\rm ac}^{0.5}$ Linder the Funsiciple, and toilet. Therefore, use directions are not appropriate.]

[Claims are limited to sanitization. No claims for disinfection are read micett 2

#### ASPHALT OR WOOD ROOFS AND SIDINGS

To control fungus and mildew, first remove all physical soil by brushing and hosing with clean water, and apply a 5000 ppm available chlorine solution. Mix 1 oz. of this product per gallon of water and brush or spray roof or siding. After 30 minutes, rinse by hosing with clean water.

# BOAT BOTTOMS

To control slime on boat bottoms, sling a plastic tarp under boat, retaining enough water to cover the fouled bottom area, but not allowing water to enter enclosed area. This envelope should contain approximately 500 gallons of water for a 14 foot boat. Add 3.5 oz. of this product to this water to obtain a 35 ppm available chlorine concentration. Leave immersed for 8 to 12 hours. Repeat if necessary. Do not discharge the solution until the free chlorine level has dropped to 0 ppm, as determined by a swimming pool test kit.

# ARTIFICIAL SAND BEACH

To sanitize the sand, spray a 500 ppm available chlorene solut lining 0.1 cz. of this product per gallon of water at frequent intervals as can be sprinkled with a watering can.

FOOD PROCESSING PLANTS

POULTRY DRINKING WATER - Spray or flush with a solution containing 1 oz. of this product for every gallon of water. Treat poultry drinking water to a dosage of 1 to 5 ppm available chlorine by adding 1 to 5 oz. of this product per 1000 gallons of water.

FISH FILLETING - Eviscerated and degilled fish removed from the fishing vessel are placed in a wash tank of seawater or fresh water which has been treated with enough product to produce a chlorine residual of 25 ppm, as determined by a test kit. Remove fish from treated water 24 to 48 hours before filleting. After scaling the fish are again washed in a 25 ppm solution, and are ready for filleting.

PECAN CRACKING AND DYEING - Prepare a 1000 ppm available chlorine soaking solution by adding 1 oz. of this product for each 5 gallons of water to obtain a 1000 ppm available chlorine content. Soak for a minimum of 10 minutes. After removal, age pecans for 24 hours. Before bleaching, pecans are placed in a rotary cleaner where they are washed, drained, and soaked in a 2% sulphuric acid bath at 80 to 90°F for 1 minute. Transfer to a solution containing 100 oz. of this product for each 100 gallons of water (5000 ppm). After 4 to 8 minutes, they are drained and washed in a 1% sulphuric acid bath at 80 to 90°F. They are then dried.

BACTERIAL CONTROL IN SUGAR REFINERARS - To reduce dust-collecting-bacteria, apply a solution containing 16 oz. of this product for each gallon of water (8000 ppm. available chlorine) continuously by gravity into the recirculating low doncentration syrup/in the dust/collector, Adjust the feed to give a chlorine residual of about 10 ppm in the syrup leaving the dust collector system. To reduce gum-forming bacteria, coat raw sugar with a solution of low concentration of product to control bacteria. To control of thermophillic bacteria in vacuum pans, feed a solution containing 1 pound of this product for each ton of sugar (dry weight) in the vacuum pans.

FOR USE IN EMERGENCY CARE AREAS: Fire Departments, Ambulance Services, Rescue Squads and Hospital Emergency Departments for the rapid decontamination of patient handling devices such as stretchers, cots, scoop stretchers, as well as splinting divices and ambulance floors. Unit will provide 600 ppm (1.2 oz. of this product per 10 gallons of water)

18

18 7 18

-Banove gross sitt of neary sail by thorough clean the surfaces prior to application. For use as spray to wet all surfaces thoroughly. Apply for A minutes.

# as a termind revilant/high land lisinfectant

This product is not to be Msed on any surface or instrument that (1) is introduced directly into the human body, either into or in contact with the bloodstream or mormally sterile areas of the body, or (2) contacts intact mucous membranes but which does not ordinarily penetrate the blood barrier or otherwise enter normaily sterile areas of the body. This product may be used to preclean of decontaminate critical or semi-critical medical devices prior to sterilization or high level disinfection.