

CAUTION: Keep Out of the Reach of Children

CAUTION: Harmful f .waifawed Avoid contact with skin. Wash thoroughly after using, Stude in a same place away from feed and food products.

ANTIDOTE: if taken internally, induce vomiting and call physician at once

READ ENTIRE LABEL BEFORE USING THIS PRODUCT.

WARRANTY - CONDITION OF SALE: DIRECTIONS FOR USE of this product are based on field use and tests believed reliable and should be followed carefully. It is however impossible to eliminate all risks associated with use of this product. Because such factors as weather conditions, foreign material and manner of use for application are all beyond the control of The Ansul Company or the Seller of the product, such things as crop injury, ineffectiveness or other unintended consequences may result. ALL SUCH RISKS TE ASSUMED BY THE BUYER.

Ansul warrants that this product confirms to the chemical description on the label and is reasonably fit for the purposes referred to in the directions for use as modified by the above. Ansul makes no other warranties, express or implied, including FITNESS or MERCHANTABILITY, In no case shall Ansul or the Seiler be liable for consequential, special or indirect damages resulting from the use or handling of this product. The foregoing is a condition of sale by The Ansul Company and is accepted as such by the Buyer. GENERAL INFORMATION: SILVISAR 550 Tree Killer is designed for crown kill of undesirable trees through spaced-cut injection methods. It is useful for the control of the following conifers: ludgepole pine, ponderosa pine, Douglas-fir, jack pine, and red pine. It is also useful for the control of big leaf maple. It shows negligible translocation through root grafts and has no residual phytotoxic action in the soil. CARE OF EQUIPMENT: SILVISAR 550 Tree Killer is entirely soluble in water. Rinse all injection equipment thoroughly after use, and dispose of figuid wastes in a pit in non-crop lands located away from water supplies.

CONTAINER DISPOSAL: Do not reuse empty container. Wash thoroughly with water and detergent, crush if possible, and discard in a safe place.

DIRECTIONS FOR USE:

SPACED-CUT INJECTION WITH ANSUL "HYPO-HATCHET" INJECTOR: The Assur HYPO-HATCHET Injector cits and injects in one operation. When a tree is struck with the injector, a pre-set amount of SILVISAR 550 Tree Killer is injected automatically into the sapstream of the tree immediately after impact. The injector works by mertia and is designed to inject at least one millinter of chemical per stroke. The cuts should be evenly spaced around the trunk to give proper distribution into the sapvicod. For detailed instructions on how to use the Ansul HYPO-HATCHET Injector, refer to the Operation Manual.

CONIFERS (See General Information) AND BIG LEAF MAPLE (Growing Season) - For trees below 8 inches diameter at breast height (DBH), make one cut per 2 inches of DBH (4%" spacing between out edges) at waist height or below. For trees 8 inches DBH and larger, make one cut per 1 inch DBH '1%" spacing between out edges).

CONIFERS (Dormant Season) - Make one cut per 1 inch of DBH (11/4" spacing between our edges) at waist height or below

BIG LEAF MAPLE (Dormant Season) - Make a complete frill at waist height or below (cuts need not be overlapping).

SPACED-CUT APPLICATION: Although spaced-cut application is facilitated by use of the Ansui HYPO-HATCHET Injector, a hatchet or similar cutting tool can be used. The number of cuts per tree depends upon the size of the cuts and the volume to be injected, but in any case, should be sufficient to hold the silvicide without running down the trunk. Make certain that each cut penetrates into the sapwood. Apply SILVISAR 550 Tree Killer with a pump-type oil can, plastic squeeze bottle, or other suitable dispenser. CONIFERS (Sae General Information) AND BIG LENF MAPLE (Growing Season) - For trees below 8 inches diameter breast height (DBH), apply 1 to 2 milliliters of SILVISAR 550 Tree Killer per out per 2 inches of DBH 16" spacing between out centerlines) at waist height or below. For trees 8 inches DBH and larger, use 1 to 2 milliliters per out per 1 inch DBH (3" spacing between centerlines).

CONIFERS (Dormant Season) - Apply 1 to 2 milliliters of SILVISAR 550 Tree Killer per cut per 1 each of DBH (3" spacing between our centerlines).

BIG LEAF MAPLE (Dormant Season) - Apply 1 to 2 milliters of SILVISAR 550 Tree Kaller per rur in a complete frill at waist height or below. (Cuts need not be overlapping)

SILVISAR 550 Tree Killer is manufactured by The Ansul Company, Marinette, Wisconsin 54143 X. SILVISAR, HYPG-HATCHET, ANSUL are registered trademarks of The Ansul Company EPA Reg. No. 6308-58 Net Contents 5 Gallons Patent Pending

Form No.



THE ANSUL COMPANY MARINETTE, MISCONSIN New Disclaimer Statement Added To Label as Follows:

WARRANTY - CONDITION OF SALE: DIRECTIONS FOR USE of this product are based on field use and tests believed reliable and should be followed carefully. It is however impossible to eliminate all risks associated with use of this product. Because such factors as weather conditions, foreign material and manner of use for application are all beyond the control of The Ansul Company or the Seller of this product, such things as crop injury, ineffectiveness or other unintended consequences may result. ALL SUCH RISKS ARE ASSUMED BY THE BUYER.

Ansul warrants that this product conforms to the chemical description on the label and is reasonably fit for the purposes referred to in the directions for use as modified by the above. Ansul makes no other warranties, express or implied, including FITNESS or MERCHANTABILITY. In no case shall Ansul or the Seller be liable for consequential, special or indirect damages resulting from the use or handling of this product. The foregoing is a condition of sale by The Ansul Company and is accepted as such by the Buyer.

