

ACCEPTED
35772-3
AUG 1 9 1966
U.S. Food & Drug Administration

**Precautionary Statements
Hazards to Humans
and Domestic Animals**

WARNING

Harmful if swallowed, inhaled or absorbed through the skin. Avoid breathing dust. Avoid contact with skin, eyes, or clothing. May cause eye damage or severe skin irritation.

**PHYSICAL AND CHEMICAL HAZARDS
STRONG OXIDIZING AGENT:**

Strong Oxidizing Agent. Mix only with water. Use clean dry utensils. Do not mix this product with any other chemical or gross filth. Such use may cause a violent reaction leading to fire or explosion. Contamination with moisture, organic matter, or other chemicals may start a chemical reaction, with generation of heat, liberation of hazardous gases, and possible generation of fire and explosion. In case of contamination or decomposition, do not reseal container. If possible isolate container in open air or well ventilated area. Flood with large volumes of water, if necessary.

NET CONTENTS

**ECONO-CHLOR
DETERGENT SANITIZER**

ACTIVE INGREDIENTS

Sodium dichloro-s-triazinetriane dihydrate (provides 3.2% available chlorine)	5.6%
Sodium dodecylbenzene sulfonate	4.0%
Sodium metasilicate	5.0%

INERT INGREDIENTS

85.4%

KEEP OUT OF REACH OF CHILDREN

WARNING

Harmful if swallowed. May cause eye damage. Do not get in eyes, on the skin or on clothing. Do not breathe dust. If swallowed, feed gravel or cooked cereal followed by olive oil or cooking oil. Call physician. In case of personal contact, remove excess material and flush skin or eyes with fresh water for at least 15 minutes. For eyes get medical attention. Rinse empty container thoroughly with water and discard it. See side panel for use directions.

ECONO-CHLOR DETERGENT SANITIZER

Recommended for use on food processing equipment and utensils including dairy and brewery equipment and utensils. It is also recommended for use on dishes and glasses.

EPA REGISTRATION # 35772-3

Manufactured by Establishment # 15721201

DIRECTIONS FOR USE:

It is a violation of a Federal law to use this product in a manner inconsistent with its labeling.

Prepare a sanitizing solution by dissolving 4 1/2 oz. or 8 1/2 oz. ECONO-CHLOR DETERGENT SANITIZER per 10 gal. of water. This provides a solution containing 100 ppm or 200 ppm of available chlorine respectively. Clean and rinse items prior to sanitizing. Then place glasses, dishes, equipment or utensils in solution for 2 to 5 minutes. Remove, rinse with potable water and dry. For flat surfaces clean to remove gross filth and heavy soil. Then spread the sanitizing solution and allow to stand 2 to 5 minutes and then rinse with potable water.

The same solution may be used in feed tank in immersion or spray type machines providing 2 to 5 minutes contact time for sanitizing dishes, glasses, food processing equipment and utensils. Clean and rinse items prior to sanitizing. After sanitizing step, rinse well with potable water and dry. The items are then ready for use.

The sanitizing solution should be used promptly after mixing. If the solution is allowed to stand or if analysis and tests show the level of chlorine has not been maintained, additional ECONO-CHLOR DETERGENT SANITIZER should be added, to maintain a minimum concentration of 100ppm available chlorine.

STORAGE AND DISPOSAL

Store in a cool, dry, well ventilated area. Moisture contamination may operate irritating and hazardous chlorine containing bases. Oxidizing material. Do not mix with other chemicals. Contact with organic matter may cause fire. Decomposes at 350-475 F with liberation of harmful gases. In case of decomposition, place the container in open air or well ventilated area. Flood with large volume of water to neutralize.

Do not reuse empty container. Rinse empty container thoroughly with fresh water before discarding.

The product is toxic to fish. Treated effluent should not be discharged where it will drain into lakes, streams, or other bodies of water. Do not contaminate water with cleaning or disposal of wastes. Apply this product only as specified on label.