



# WEED STOPPER HOSE 'EM™

Alternate Brand Name – WEED IMPEDE™ HOSE 'EM™

### Selective Preemergence Herbicide

- Controls growth of annual grasses and broadleaf weeds in flower beds, groundcovers, ornamental beds, around shrubs and trees, and in driveways, walkways and other non-planted areas
- Just attach to a garden hose and spray
- Covers 1,000 square feet (1,250 square feet)
- Refillable

ACCEPTED

JUL 21 2005

Under the Federal Insecticide, Fungicide, and Rodenticide Act as amended, for the pesticide registered under EPA Reg. No.

54705-11

Active Ingredient:	
Oryzalin: 3,5-dinitro-N,N'-dipropylsulfanilamide .....	3.0%
Other Ingredients:.....	97.0%
Total.....	100.0%

Contains 0.25 pounds active ingredient per gallon.

EPA Reg. No. 54705-11  
WEED IMPEDE and HOSE 'EM are trademarks of Lawn and Garden Products, Inc.

EPA Est. No. 48498-CA-1

**NET CONTENTS: 24 FL. OZ. (1 PT. 8 FL. OZ.)**  
**[30 FL. OZ. (1 PT. 14 FL. OZ.)]**

Manufactured For:  
**LAWN AND GARDEN PRODUCTS, INC.**  
P. O. Box 35000 • Fresno, CA 93745 • (559) 499-2100  
www.montereylawngarden.com

## KEEP OUT OF REACH OF CHILDREN CAUTION

### FIRST AID

- If In Eyes:**
- Hold eye open and rinse slowly and gently with water for 15-20 minutes.
  - Remove contact lenses, if present, after 5 minutes, then continue rinsing.
  - Call a poison control center or doctor for treatment advice.

### HOT LINE NUMBER

Have the product container or label with you when calling a poison control center or doctor or going for treatment. You may also contact the National Pesticide Information Center at 1-800-858-7378 for emergency medical treatment information.

### PRECAUTIONARY STATEMENTS HAZARDS TO HUMANS AND DOMESTIC ANIMALS

**CAUTION:** Causes moderate eye irritation. May cause skin allergies to develop. Avoid contact with skin, eyes or clothing. Wear a long-sleeved shirt, long pants, chemical-resistant gloves, and shoes plus socks when applying this product. Remove contaminated clothing and wash before reuse. Keep all persons, children, and pets out of treated area until sprays have dried.

---

**ENVIRONMENTAL HAZARDS**

This pesticide is toxic to fish. Do not apply directly to water, or to areas where surface water is present or to intertidal areas below the high water mark. Drift and runoff from treated areas may be hazardous to aquatic organisms in adjacent aquatic sites. Do not contaminate water when disposing of equipment washwaters or rinsate.

**DIRECTIONS FOR USE**

It is a violation of Federal law to use this product in a manner inconsistent with its labeling. For household use only.

**What Is This Product? And What Will It Do?**

WEED STOPPER HOSE 'EM is the easy way to have beautiful, weed-free flower beds as well as weed-free driveways, walkways and other non-planted areas all year round. Once you've cleaned out the weeds and grass already growing around your flowers, shrubs and trees, WEED STOPPER HOSE 'EM keeps them from coming back. And it lasts up to 4 months!

Now you can plant your zinnias, pansies or marigolds, spray with WEED STOPPER HOSE 'EM, then sit back and watch them grow. No more hands-and-knees weeding for you.

This easy-to-use container attaches right to your garden hose, so there's no mixing. Use only what you need, then put it away for next time. When the container is empty, simply throw it away.

**How Do I Use This Product?**
**When To Use:**

For established beds and borders, you can use WEED STOPPER HOSE 'EM anytime throughout the growing season. But, the area must be free of weeds and grass, before you spray. Re-spray every 3 to 4 months to keep the areas free of weeds.

**What To Do:**

Shake well before using. WEED STOPPER HOSE 'EM won't work on weeds and grasses already growing. So, you have to remove them before you get started. When you are finished preparing the area, you can spray.

**How To Use This Sprayer: Shake container well before getting started.**

1. Before you start, the blue flow switch should be in the "OFF" position, and the red flow switch should be in the up, "CLOSED" position.
2. Shake container well and attach it to your garden hose, while holding sprayer at waist level and pointing in a direction away from face and body.
3. Turn on the water from the faucet.
4. When you are ready to spray, turn the blue flow switch to "ON" position; turn red flow switch to the forward, "OPEN" position; and begin spraying.
5. When you are finished spraying or if you have to stop spraying at any time, turn the blue flow switch back to the "OFF" and the red flow switch to the "CLOSED" position.
6. Turn off the water at the faucet.
7. Remove the container from the garden hose; then rinse thoroughly and store according to storage instructions.

**How To Refill This Sprayer:**

Remove spray head. Add 2 fluid ounces of Weed Stopper (Weed Impede), EPA Reg. No. 547C5-5 to spray container. Fill remainder of container with water. Reattach spray head. Shake well and continue spraying.

Spray WEED STOPPER HOSE 'EM evenly over the soil and the plants (i.e., right over the top of the leaves), but avoid areas where bulbs are planted. The orange color lets you see where you have sprayed and prevents skips or overlaps. This whole bottle will cover 1,000 square feet (20' x 50') [1,250 square feet (20' x 62.5')]. Water the area with clear water for about ½ hour after treating.

**For Barkdust Areas Or Other Mulch Covers:** Wet the area well with clear water before spraying with WEED STOPPER HOSE 'EM. Water again afterwards.

---

**What Not To Do:**

Do not use WEED STOPPER HOSE 'EM around vegetables, fruits or other edible plants. Do not use on lawns or dichondra. Do not treat steep areas, where product may move downhill. Do not use over newly planted ice plant. Wait several weeks, until ice plant is well rooted, before applying WEED STOPPER HOSE 'EM.

Do not use this product around these plants; they will be damaged: Techny arborvitae, Eastern (Canada) hemlock, or Slender deutzia.

Once an area is treated, do not dig in or otherwise disturb the soil surface. Weeds may pop up. Do not plant seeds, seedlings or other shallow rooted plants in a treated area until 4 months have passed. They may be damaged.

WEED STOPPER HOSE 'EM is orange in color. It will stain paint, stucco, wood, cement, brick, gravel clothing and many other surfaces around the house. Do not allow this product to contact any of these. Do not allow adults, children or pets back onto the sprayed area until it has dried.

**What Will I See?**

You will see beautiful flower beds with no weeds to spoil the view. You will see clean, tidy shrub beds, and weeds will no longer spring up around trees, in gravel walkways and driveways.

---

**STORAGE AND DISPOSAL**

Do not contaminate water, food or feed by storage or disposal.

**STORAGE:** Avoid freezing. Store above 40°F. Store in original container only and keep in a locked storage area out of reach of children and domestic animals. Rinse equipment thoroughly with water after using.

**CONTAINER DISPOSAL:** If empty: Do not reuse this container. Place in trash or offer for recycling if available. If partly filled: Call your local solid waste agency or 1-800-CLEANUP for disposal instructions. Never place unused product down any indoor or outdoor drain.

**NOTICE TO BUYER**

Seller warrants this product conforms to its chemical description on this label and is reasonably fit for the purposes stated on this label when used in accordance with directions under normal use conditions. This warranty does not extend to use of this product contrary to label directions, or under abnormal use conditions, or under conditions not reasonably foreseeable to seller. Buyer assumes all risk of any such use. Seller makes no other warranties, either express or implied.

0801/0505(02)

**[OPTIONAL HOSE-END SPRAYER DIRECTIONS]**

1. Make sure knob is twisted fully clockwise to OFF position. Shake well before attaching to hose.
2. Turn Product Control Button clockwise until its point aligns with triangle, then push all the way in. Avoid squeezing bottle.
3. Turn water on at faucet, aim nozzle toward lawn and turn knob counter clockwise to begin spraying.
4. When finished push Product Control Button to OFF position from opposite side. Return knob and faucet to OFF position.
5. Discharge water pressure by turning knob ON and OFF again.
6. Turn Product Control Button counter clockwise away from triangle to prevent accidental discharge.
7. Rinse container thoroughly and store according to Storage Instructions.