



TREE GUARD®

DEER REPELLENT

READY
TO USE

Deer repellent for reduction of feeding by deer on
**CONIFERS AND DECIDUOUS, NON-BEARING
TREES, SHRUBS, FLOWERS AND OTHER
ORNAMENTAL PLANTS**

ACTIVE INGREDIENT:

Denatonium benzoate, Benzyldiethyl [(2,6 xylyl
carbamoyl) methyl] ammonium benzoate 0.20%*
OTHER INGREDIENTS 99.80%

Total 100.00%

* Contains 0.017 lbs. (7.76 g) active ingredient (also
known as Bitrex) per gallon.

EPA Reg. No. 66676-1 EPA Est. 67064-IA-001



**KEEP OUT
OF REACH
OF CHILDREN
CAUTION**

See back panel
for additional precautions

**KEEP FROM
FREEZING**

.....
**BECKER
UNDERWOOD®**

801 Dayton Ave ■ PO Box 667
Ames, IA 50010 USA
800-232-5907
Fax 515-232-5961
www.treeguard-deer

2LBL000155
8/01

NET CONTENTS: 1 Gallon

JAN 28 2002

Under the Federal Insecticide,
Fungicide, and Rodenticide Act,
as amended, for the pesticide
registered under
EPA Reg. No. 66676-1

TREE GUARD® Deer Repellent

DIRECTIONS FOR USE

It is a violation of Federal law to use this product in a manner inconsistent with its labeling.

USE RESTRICTIONS: This product may be used to discourage deer (*Odocoileus* spp.) from feeding on shrubs, ornamental plants, conifers, and nonbearing deciduous trees. Use this product only at ambient temperatures between 40°F and 90°F. Where deer pressure is high, consider other abatement options including fencing. Do not use on food or feed crops. **Do not apply aerially.** Do not apply product through any type of irrigation system or hose proportioner applicator. Do not apply directly to or where product might drift onto stone, concrete or siding as staining might occur. TREE GUARD® has been tested on many species of ornamental plants and is believed not to be generally phytotoxic. Nevertheless, it is advisable to test the product on types of plants that might be especially sensitive by treating and observing small portions of the plant before treating the entire plant.

APPLICATION DIRECTIONS: This product is ready-to-use and should not be diluted. Shake container well before using product. Apply TREE GUARD® directly using the squeeze trigger applicator. If the container lacks a squeeze trigger, transfer product to any pump-type sprayer equipped with a cone or flat fan nozzle. Adjust nozzle to obtain even coverage. Apply only to dry plants. Hold spray tip 1 to 2 feet from plants to be treated and spray leaves, needles, buds, branches and trunks subject to browsing by deer. Thoroughly wet treated surfaces but do not apply to the point of significant spray run-off. For small shrubs such as global arborvitae 20-24" high, approximately 4-5 plants can be treated with the contents of a 1-quart container. Less product per plant will be needed for treating smaller, or less densely foliated plants; larger, heavily foliated plants will require greater amounts of product. Repeat treatments if deer damage resumes. For best results, apply to bare branches in fall, after the first frost, and to unprotected foliage in spring.

CLEAN APPLICATION EQUIPMENT IMMEDIATELY BEFORE SPRAY DRIES.

PRECAUTIONARY STATEMENTS

HAZARDS TO HUMANS AND DOMESTIC ANIMALS

CAUTION: Harmful if absorbed through the skin. Avoid contact with eyes, skin or clothing. Wash thoroughly with soap and water after handling.

FIRST AID

Have the product container or label with you when calling a poison control center or doctor, or going for treatment.

If on skin
or
clothing

- Take off contaminated clothing.
- Rinse skin immediately with plenty of water for 15-20 min.
- Call a poison control center or doctor for treatment advice.

ENVIRONMENTAL HAZARDS: Do not apply directly to water, to areas where surface water is present or to intertidal areas below the mean high water mark. Do not clean equipment or dispose of equipment wash waters in a manner that will contaminate water resources or arable land.

STORAGE AND DISPOSAL:

Storage: Store only in original container, in a dry place inaccessible to children and pets. **KEEP FROM FREEZING.**

Product Disposal: Wastes resulting from the use of this product may be disposed of on site or at an approved waste disposal facility.

Container Disposal: Do not reuse empty container. Rinse thoroughly and wrap in several layers of newspaper before discarding in trash.

NOTICE: Becker Underwood, Inc. makes no express or implied warranties of fitness or merchantability or any other kind whatsoever, except that the product conforms to the specifications on the label. Becker Underwood, Inc.'s sole liability on the warranty is limited, at Becker Underwood's option, to replacement of the defective product or return of the purchase price paid for the defective product. Under no circumstances shall Becker Underwood, Inc. be liable for incidental, consequential or special damages. The buyer assumes all risks and liability resulting from the use of this product, whether used singly or in combination with other goods. Becker Underwood, Inc. neither assumes, nor authorizes any person to assume for it, any other liability in connection with the sale or use of this product.



2LBL000154 8/01