

SCEPTER(R) herbicide

Supplemental Labeling

4036

EPA Reg. No. 241-289

FOR USE IN SOYBEANS

FOR CONTROL OF HEMP SESBANIA AND HOPHORNBEAM COPPERLEAF IN SCEPTER TREATED SOYBEANS.

A tankmix of SCEPTER in combination with Sencor or Lexone plus PROWL(R) herbicide, Treflan, trifluralin, Lasso or Dual may be applied preplant incorporated in soybeans. This treatment will control hemp sesbania (Sesbania exaltata) and hophornbeam copperleaf (Acalypha ostryaefolia) in addition to the weeds controlled by a soil application of SCEPTER and the grass herbicide.


DIRECTIONS FOR USE

OBSERVE ALL PRECAUTIONARY STATEMENTS AND LIMITATIONS IN THE SCEPTER LEAFLET LABEL BEFORE USING.

APPLICATION INSTRUCTIONS:

Apply 2/3 pint of SCEPTER per acre plus PROWL, Treflan, trifluralin, Lasso or Dual plus Sencor or Lexone before planting and incorporate uniformly into the top 1 to 2 inches of soil. Refer to the SCEPTER leaflet label for rates of the grass herbicide and incorporation instructions. Observe all precautions and limitations on the PROWL, Treflan, trifluralin, Lasso or Dual label. Apply Sencor or Lexone at a the rate specified in the label below.

	Sencor or Lexone Rate*	
	4.0 L	75 % DF
Coarse Soils	1/2 pint	1/3 lb
Medium Soils	1/2 pint	1/3 lb
Fine Soils	2/3 pint	1/2 lb



*DO NOT use Sencor or Lexone on coarse soils of less than 2% organic matter. Use 1/2 lb or 2/3 pint of Sencor or Lexone on medium soils of greater than 4% organic matter.

Observe all precautions and limitations on the Sencor or Lexone label.

(R) Registered Trademark of American Cyanamid Company



EPA Reg No. 241-289

FOR USE IN SOYBEANS

FOR THE CONTROL OF PIGWEED AND COCKLEBUR WHICH HAVE ESCAPED FROM A SOIL APPLICATION OF 2/3 PINT/ACRE OF SCEPTER DUE TO ADVERSE WEATHER CONDITIONS.

OBSERVE ALL PRECAUTIONARY STATEMENTS IN THE SCEPTER LEAFLET LABEL BEFORE USING.

Postemergence

A rate of 1/3 pint per acre of SCEPTER® herbicide will provide control of existing cocklebur and pigweed species (not over 6" tall) which have escaped from a 2/3 pint per acre soil application of SCEPTER due to adverse weather conditions.

Apply this treatment when weeds are actively growing. DO NOT apply SCEPTER postemergence when soybeans and weeds have been subjected to stress conditions such as temperature and moisture extremes. There must be an interval of at least 90 days between the last SCEPTER application and soybean harvest.

This postemergence application of SCEPTER may follow a soil application of SCEPTER in Alabama, Arkansas, Florida, Georgia, Illinois (south of Interstate 70), Indiana (south of Interstate 70), Kentucky, Louisiana, Mississippi, Missouri (south of Interstate 70), North Carolina, Oklahoma, South Carolina, Tennessee and Texas only.

MIXING AND SPRAYING

Fill the spray tank one-half to three-quarters full with clean water. While agitating add the required amount of SCEPTER and then fill the remainder of the tank with water. Add a nonionic surfactant, at least 80% concentrated, or a crop oil concentrate as the last ingredient in the tank. The rate of the nonionic surfactant should be 2 pints per 100 gallons of spray mixture. Use the recommended labeled rate for the crop oil concentrate. Maintain agitation while spraying to ensure a uniform spray mixture. An antifoaming agent may be added to the tank if needed.

Uniformly apply with properly calibrated ground equipment in 20 or more gallons of water per acre. Use sprayers equipped with nozzels that provide accurate and uniform application. To minimize drift, use a maximum spray pressure of 40 psi. Use higher gallonage for fields with dense vegetation.


®SCEPTER is a registered trademark of American Cyanamid Company



CYANAMID

American Cyanamid Company
Agricultural Division
Crop Protection Chemicals Department
Wayne, NJ 07470

© 1984



60633

SCEPTER(R) herbicide

Supplemental Labeling

EPA Reg. No. 241-289

FOR USE IN SOYBEANS

FOR CONTROL OF HEMP SESBANIA AND HOPHORNBEAM COPPERLEAF IN SCEPTER TREATED SOYBEANS.

SCEPTER plus PROWL(R) herbicide, Treflan, trifluralin, Lasso or Dual preplant incorporated followed by a preemergence application of Sencor or Lexone may be applied in soybeans. This treatment will control hemp sesbania (Sesbania exaltata) and hophornbeam copperleaf (Acalypha ostryaefolia) in addition to the weeds controlled by a soil application of SCEPTER and the grass herbicide.


DIRECTIONS FOR USE

OBSERVE ALL PRECAUTIONARY STATEMENTS AND LIMITATIONS IN THE SCEPTER LEAFLET LABEL BEFORE USING.

APPLICATION INSTRUCTIONS:

Apply 2/3 pint of SCEPTER per acre plus PROWL, Treflan, trifluralin, Lasso or Dual before planting and incorporate uniformly into the top 1 to 2 inches of soil. Refer to the SCEPTER leaflet label for rates of the grass herbicide and incorporation instructions. Observe all precautions and limitations on the PROWL herbicide, Treflan, trifluralin, Lasso or Dual label. Apply Sencor or Lexone preemergence at a the rate specified in the label below. For banding instructions refer to the Sencor or Lexone label.

		Sencor or Lexone Rate*
	4.0 L	75 % DF
Coarse Soils	1/2 pint	1/3 lb
Medium Soils	1/2 pint	1/3 lb
Fine Soils	2/3 pint	1/2 lb



*DO NOT use Sencor or Lexone on coarse soils of less than 2% organic matter. Use 1/2 lb or 2/3 pint of Sencor or Lexone on medium soils of greater than 4% organic matter.

Observe all precautions and limitations on the Sencor or Lexone label.

(R) Registered Trademark of American Cyanamid Company

