

FRONT PANEL

U-DO-IT
 SINCE 1929
arab[®]
TERMITE CONTROL
 CONCENTRATE

FOR HOMEOWNER USE
 MAKES 100 GALLONS WHEN MIXED WITH WATER

ACTIVE INGREDIENTS:

Technical Chlordane*	72.0%
Petroleum Distillate	23.0%
INERT INGREDIENTS:	5.0%
Total:	100.0%

*equivalent to 43.2% of octachloro-4, 7-methano-tetrahydroindane and 28.8% of related compounds.

EPA Reg. No. 654-12-AA
 EPA Est. 654-IN-1

ILLUSTRATED INSTRUCTION BOOKLET ATTACHED

"5 YEAR CHEMICAL REPLACEMENT AGREEMENT"
 APPLICATION AVAILABLE

CONTENTS 1/2 U.S. GALLON

KEEP OUT OF REACH OF CHILDREN

WARNING
 SEE BACK PANEL FOR ADDITIONAL
 PRECAUTIONARY STATEMENTS

ACCEPTED
 APR 27 1984
 Under the Federal Insecticide, Fungicide, and Rodenticide Act as amended, for the Pesticide registered under EPA Reg. No. 654-12

BEST DOCUMENT AVAILABLE

7

PRECAUTIONARY STATEMENTS
Hazards to Humans & Domestic Animals
WARNING

May be fatal if swallowed. Do not breathe vapor or spray mist. Do not get in eyes, on skin or clothing. In case of skin contact, wash immediately with soap and water. Avoid contamination of feed and foodstuffs.

STATEMENT OF PRACTICAL TREATMENT

If Swallowed--Call a physician or Poison Control Center immediately. Drink one or two glasses of water and induce vomiting by touching the back of throat with finger. Repeat until vomit fluid is clear. Do not induce vomiting or give anything by mouth to an unconscious person.

If Inhaled--Remove victim to fresh air. Apply artificial respiration if indicated.

If on Skin--Remove contaminated clothing and wash affected areas with soap and water.

If in Eyes--Flush eyes with plenty of water. Call a physician if irritation persists.

ENVIRONMENTAL HAZARDS

This product is toxic to fish, birds, and other wildlife. Keep out of lakes, streams and ponds. Do not contaminate water by cleaning of equipment or disposal of wastes. Apply this product only as specified on this label.

PHYSICAL OR CHEMICAL HAZARDS

Do not use, pour, spill or store near heat or open flame.

HOW ARAB U-DO-IT WORKS

U-DO-IT, used according to directions, sets up an effective chemical barrier in the soil and protects homes and other structures against attack by subterranean termites. They live in nests in the soil and they move out from their nests in search of wood or wood products for food. If they leave the soil and enter buildings, they must frequently return to the soil for moisture or they die. The chemical barrier set up by proper application of U-DO-IT will kill termites which tunnel through the treated soil. It not only prevents termites from entering, but will also cause the death of any termites within the structure since it cuts them off from the soil. If you have a special problem, write to our Technical Director.

Will not harm lawns, shrubbery, or flowers

CONTAINER DISPOSAL

Do not reuse empty container.

Securely wrap original container in several layers of newspaper and discard in trash.

FEDERAL CHEMICAL CO., INC.
INDIANAPOLIS, INDIANA 46268

BEST DOCUMENT AVAILABLE

DIRECTIONS FOR USE

It is a violation of federal law to use this product in a manner inconsistent with its label.

MIXING DIRECTIONS

FOR EASIEST APPLICATION USE AN ARAB PROFESSIONAL APPLICATOR available at your dealer. It attaches to a garden hose and delivers either a 1% or a 1/2% Chlordane emulsion. Detailed mixing directions are printed on Applicator.

FOR USE WITH SPRINKLING CAN OR PRESSURE TYPE GARDEN SPRAYERS: Thoroughly mix 1 part of U-DO-IT concentrate with 199 parts of water (4 teaspoons per gallon) for a 1/2% emulsion, or 1 part of U-DO-IT concentrate with 99 parts of water (2-1/2 tablespoons per gallon) for a 1% Chlordane emulsion.

A minimum of 5 years' control is obtained by use of a 1% emulsion if applied according to the following directions. If the 1/2% emulsion is used, the property should be inspected annually for possible reinfestation and retreatment if necessary. Even with the 1% emulsion, annual inspections are desirable in case any areas were missed in the initial treatment.

SUBTERRANEAN TERMITES - DIRECTIONS FOR HOMEOWNER USE

Outside Treatment

BUILDINGS HAVING BASEMENT OR CRAWL SPACES: Around piers, pipes, chimney bases and along foundations of poured concrete dig a trench 6 inches wide and 4 inches deep. For brick and block foundations dig the trench about 12 inches deep. If footing is more than 12 inches deep, make holes with a crowbar, pipe or a rod about one foot apart that extend from the trench bottom to the top of the footing. Make holes closer in hard-packed clay soils. NEVER DIG BELOW THE TOP OF THE FOOTING. Apply the mixed U-DO-IT in the trench at a rate of 4 gallons per 10 linear feet per foot of depth. Apply half of this to the back-fill. Likewise, treat along the inside of foundations of crawl-space buildings. Cover treated soil with a thin layer of untreated soil.

FOR RAISED PORCHES, TERRACES, AND ENTRANCE SLABS: Drill holes at one foot intervals, 6 inches from the foundation, and pour one-half gallon of mixed U-DO-IT into each hole. Refill holes. Slabs with heat ducts or radiating heat pipes should be treated by commercial pest control operator.

Inside Treatment

CRAWL SPACES: First remove all wood debris and wood forms. Around piers, pipes, chimney bases, and along foundations of poured concrete dig a trench 6 to 8 inches wide and 4 inches deep. For brick and hollow block foundations dig the trench about 12 inches deep, make holes in soil to footing as specified above. NEVER DIG BELOW THE TOP OF THE FOOTING. Apply mixed U-DO-IT at the rate of 4 gallons per 10 linear feet per foot of depth. Apply half of this to the back-fill. Cover treated soil with a thin layer of untreated soil.

The object is to establish a treated soil barrier which will prevent termite entry. Other critical areas may also require treatment, particularly if there are inaccessible areas, basements or slab-type construction. It is suggested that you contact the Agricultural Cooperative Extension Service for advice or consult a Commercial Pest Control Service.

BEST DOCUMENT AVAILABLE

1

Inside Treatment
(Continued from Page 1)

Avoid contamination of public and private water supplies by following these precautions. Do not allow a hose or any type of faucet extension to reach into the termite chemical solution while filling or mixing this material with water. Use antiback-flow or anti-siphonage equipment on all filling equipment. These devices can be purchased at hardware or plumbing supply stores. Use of antiback-flow equipment will help to insure that the user of this toxic chemical will not contaminate domestic water supplies. Refer to Federal (Federal Housing Administration), state, and local specifications for safe distances of treatment areas from wells. Soil in the vicinity of wells, cisterns or ponds should not be treated if it is water saturated, subject to excessive saturation due to an accumulation of water or if the soil to be treated around the perimeter of the structure is at a grade lower than surrounding yard or property area. If this is the situation treat as follows: Do Not Apply Under Pressure. Soil should be removed to an area safe from well or domestic water contamination, treated, allowed to stand undisturbed for two to four hours then returned to the trench which has been lined with 4 mil. plastic sheeting. Be careful not to puncture the plastic sheeting when returning soil to the trench. Do not treat structures that contain cisterns or wells.

RETREATMENT RESTRICTIONS: Retreatment for subterranean termites should only be made when there is evidence of reinfestation subsequent to the initial treatment, or there has been a disruption of the chemical barrier in the soil due to construction, excavations, landscaping, etc. Reapplication should be made as a spot treatment to these areas.

Annual retreatment of the entire premises must be avoided.

BEST DOCUMENT AVAILABLE