

173

BEST DOCUMENT AVAILABLE

ACCEPTED  
EPA Label Dated:

MAR 9 1984

Under the Federal Insecticide, Fungicide, and Rodenticide Act, as amended, for the registration under EPA Reg. No. 870-85

GOLD CREST®

INSECTICIDE  
EMULSIFIABLE CONCENTRATE

FOR CONTROL OF TERMITES AND  
SWARMS OF COMMERCIAL PEST  
CONTROL OPERATORS

<b>ACTIVE INGREDIENTS:</b>	
Neotermol	37.5%
Surfactant Compounds	10.5%
Emulsifier	52.0%
<b>INERT INGREDIENTS</b>	
TOTAL	100.0%

Neotermol is a registered trademark of F. I. Schott & Co. Inc.  
Contains 2.8 lbs. actual Neotermol per gallon.

**KEEP OUT OF REACH OF CHILDREN  
WARNING**

**STATEMENT OF PRACTICAL TREATMENT**  
If swallowed—Call a physician or Poison Control Center immediately. Gastric lavage is indicated if the patient has taken less than 100 ml. DO NOT INDUCE VOMITING unless other treatment is not available. Vomiting may cause aspiration pneumonia. If it is necessary to induce vomiting, give water or tea (shots of water and meat tenderizer is best of these). Repeat until vomit fluid is clear. Do not induce vomiting or give anything by mouth to an unconscious person. If on skin—Remove contaminated clothing and wash affected areas with soap and water. If in eyes—Flush with plenty of water for 15 minutes. Contact a physician immediately if irritated. Remove victim to fresh air and apply artificial respiration, if indicated.

**SEE SIDE PANEL FOR ADDITIONAL PRECAUTIONARY STATEMENTS**

E.P.A. Reg. No. 870-85-AA  
E.P.A. Est. No. 870-70-1

NET CONTENTS:  
5 GALLONS



French need not be wider than 6 inches nor below the foundation. The emulsion should be mixed with the soil as it is being replaced in the trench. Cover the treated soil with a thin layer of untreated soil or other suitable barrier such as polyethylene sheeting.

**POST-CONSTRUCTION TREATMENTS**

Use a 0.5% water emulsion for subterranean termites other than Caprotermes spp. Mix 1 gallon of H-20 in 20 gallons of water to produce a 0.5% water emulsion. Use a 1% water emulsion for Caprotermes spp. where necessary. Mix 2 gallons of H-20 in 20 gallons of water to produce a 1% water emulsion.

Post-construction applications shall be made by injection, rodding, and/or trenching (using low pressure spray). Do not make an overall broadcast application of the product in a crawl space. Rod holes or trenches should not extend below the top of the footing.

Do not apply the product to the soil beneath a plenum air space. Do not apply the product to the soil beneath a crawlspace. Do not apply the product to the soil beneath a basement floor. Extreme caution must be taken to avoid contamination of these structural elements and arrays.

**Slab-On-Ground**  
For slab-on-ground construction apply at the rate of 4 gallons of emulsion per 10 linear feet. Applications may be made by sub-slab injection and/or trenching. Injectors should not extend beyond the top of the footings. Treat along the outside of the foundation and where necessary just beneath the slab on the inside of foundation walls. Treatment may also be required just beneath the slab along both sides of interior footing-supported walls, and sides of interior partitions and along all cracks and expansion joints.

a. Drill holes in the slab about 12 to 28 inches apart to provide a continuous chemical barrier.  
b. Where necessary, drill through the foundation walls from the outside and force the emulsion just beneath the slab either along the inside of the foundation or along all the cracks, expansion joints, and other critical areas.

c. For shallow foundations, 1 foot or less, dig a narrow trench approximately six inches wide along the outside of the foundation walls. Do not dig below the bottom of the foundation. The emulsion should be applied to the trench and the soil at 4 gallons per 10 linear feet as the soil is replaced in the trench. Cover the treated soil with a thin layer of untreated soil.

d. For foundations deeper than 1 foot follow rates for basements.

**Hollow Masonry Units of the Foundation Walls**  
Hollow block foundations or walls of masonry should be treated to make a continuous chemical barrier in voids. Apply at the rate of 2 gallons of emulsion per 10 linear feet.

**Basements**  
For basements and slab foundations which extend more than 1 foot below grade, apply at a rate of 4 gallons of emulsion per 10 linear feet per foot of depth from grade to the top of the footing. Treat the outside of the foundation by trenching and/or rodding. Sub-slab injection may be necessary just beneath the basement floor or slab along the inside of foundation walls, along cracks, along partitions, around sewer pipes, conduits, and piers, and along both sides of interior-footing-supported walls.

**Crawl Spaces**  
In crawl spaces apply at the rate of 4 gallons of emulsion per 10 linear feet per foot of depth from grade to top of footing. Application may be made by rodding and/or trenching. Do not make an overall broadcast application of this product in a crawl space. Do not apply this product to the soil beneath a plenum air space. Rod holes or trenches should not extend below the top of the footing. Treat both sides of foundation and around all piers and pipes.

- See page 173 for...
- See page 173 for...
- See page 173 for...

After Treatment  
Caution: Do not enter until safe to do so.

Do not use on...  
Do not use on...  
Do not use on...

Do not contaminate...  
Do not contaminate...  
Do not contaminate...

Do not use on...  
Do not use on...  
Do not use on...

Do not use on...  
Do not use on...  
Do not use on...

**VELSIC  
CHEMICAL CORP.**

BEST DOCUMENT AVAILABLE

876-85

2

- Trench need not be wider than 6 inches nor below the foundation. The emulsion should be mixed with the soil as it is being replaced in the trench. Cover the treated soil with a thin layer of untreated soil or other suitable barrier such as polyethylene sheeting.

**POST-CONSTRUCTION TREATMENTS**

Use a 0.5% water emulsion for subterranean termite other than Capitec/mec spp. Use 1 gallon of H-55 in 50 gallons of water to produce a 0.5% water emulsion. Use a 1% water emulsion for Capitec/mec spp. where necessary. Use 2 gallons of H-55 in 50 gallons of water to produce a 1% water emulsion.

Post-construction applications shall be made by injection, rodding, and/or trenching (using low pressure spray). Do not make an overall broadcast application of this product in a crawl space. Rad holes or trenches should not extend below the top of the footing.

Do not apply this product to the soil beneath a plenum air space.

Do not apply emulsion underlayment or heat or air conditioning ducts, vents, water and sewer lines and electrical conduits are known and identified. Exercise caution must be taken to avoid contamination of these structural elements and drains.

**Slab-On-Ground**  
For slab-on-ground construction apply at the rate of 4 gallons of emulsion per 10 linear feet. Applications may be made by sub-slab injection and/or trenching. Injections should not extend beyond the top of the footing. Treat along the outside of the foundation and where necessary just beneath the slab on the inside of foundation walls. Treatment may also be required just beneath the slab along both ends of interior footing-supported walls, one side of interior partitions and along all cracks and expansion joints.

- Drill holes in the slab about 12 to 36 inches apart to provide a continuous chemical barrier.
- Where necessary, drill through the foundation walls from the outside and force the emulsion just beneath the slab either along the inside of the foundation or along all cracks, expansion joints, and other critical areas.
- For shallow foundations, 1 foot or less, dig a narrow trench approximately six inches wide along the outside of the foundation walls. Do not dig below the bottom of the foundation. The emulsion should be applied to the trench and the soil at 4 gallons per 10 linear feet as the soil is replaced in the trench. Cover the treated soil with a thin layer of untreated soil.

For foundations deeper than 1 foot follow rates for basements.

**Hollow Masonry Units of the Foundation Walls**

Hollow block foundations or walls of masonry should be treated to make a continuous chemical barrier in voids. Apply at the rate of 2 gallons of emulsion per 10 linear feet.

**Basements**

For basements and slab foundations which extend more than 1 foot below grade, apply at a rate of 4 gallons of emulsion per 10 linear feet per foot of depth from grade to the top of the footing. Treat the outside of the foundation by trenching and/or rodding. Sub-slab injection may be necessary just beneath the basement floor or slab along the inside of foundation walls, along cracks, along partitions, around sewer pipes, conduits, and piers, and along both sides of interior footing-supported walls.

**Crawl Spaces**

In crawl spaces apply at the rate of 4 gallons of emulsion per 10 linear feet per foot of depth from grade to top of footing. Application may be made by rodding and/or trenching. Do not make an overall broadcast application of this product in a crawl space. Do not apply this product to the soil beneath a plenum air space. Rad holes or trenches should not extend below the top of the footing. Treat both sides of foundation and around all piers and pipes.

- Rad holes should be spaced (about 1 foot) to provide a continuous chemical barrier. Rad holes should not extend below the top of the footing.
- Trench need not be wider than 6 inches nor below the top of the footing. The emulsion should be mixed with the soil as it is replaced in the trench. Cover the treated soil with a thin layer of untreated soil or other suitable barrier such as polyethylene sheeting.
- For inaccessible crawl spaces, treat soil by an alternate method such as drilling and rodding through foundation walls from the outside.

**After Treatment**

Securely plug all holes drilled in construction elements of commonly occupied areas of structures, including unfinished basements, enclosed porches, garages, and workshops.

**RETREATMENT RESTRICTIONS**

Retreatment for subterranean termites should only be made when there is evidence of reinfestation subsequent to the initial treatment, or there has been a disruption of the chemical barrier in the soil due to construction, excavation, landscaping, etc. Retreatment should be made as a spot application to these areas.

Retreatments may be made to critical areas in accordance with the application techniques described above. This application should be made as a spot treatment to these areas. Routine or annual retreatment of the entire premises should be avoided.

**STORAGE AND DISPOSAL**

Do not contaminate water, food or feed by storage or disposal.

**PESTICIDE DISPOSAL**

Pesticide spray mixture, or rinse water that cannot be used according to label instructions must be disposed of according to Federal or approved state procedures under Subtitle C of the Resource Conservation and Recovery Act.

**CONTAINER DISPOSAL**

**Metal**  
Triple rinse (or equivalent) and offer for recycling or reconditioning, or dispose of in a sanitary landfill, or by other approved State and local procedures.

**Plastic**  
Triple rinse (or equivalent) and offer for recycling or reconditioning, or dispose of in a sanitary landfill or by incineration if permitted by State and local authorities.

**LIMITED WARRANTY AND LIABILITY**

**NOTE:** Read the Limited Warranty and Liability before buying or using the product. If the terms are not acceptable, return it to stock unopened.

It is critical that the product be used and stored only as specified on the label. No loss of a claim may result unless all of the foregoing instructions are followed. The Company's liability for any damage or injury caused by the use of this product shall be limited to the purchase price paid by the user or buyer for the quantity of product involved. Except as the label provides to the contrary, there is no warranty, and the Company and other Sellers do not have any liability for losses, personal injury or damage. It is the user's responsibility to use the product only as directed on the label and to follow all instructions on the label. The user must use the product before use with any substance except as recommended by the product label. Do not store the product in a container of other material, and do not use the product for any other purpose than that intended. Do not use the product for any other purpose than that intended. Do not use the product for any other purpose than that intended. Do not use the product for any other purpose than that intended.

ICOL

**VELSICOL**  
CHEMICAL CORPORATION  
241 E. CHASE ST., CHICAGO, IL 60611

876-85  
BEST DOCUMENT AVAILABLE

**PRECAUTIONARY STATEMENTS**  
Hazard to Humans and Domestic Animals

**WARNING**

May be fatal if swallowed. Do not breathe vapor or spray mist. Do not get in eyes, on skin, or on clothing. In case of contact, wash skin with soap and water or flush eyes with water for 15 minutes and get medical attention. See front panel for complete Statement of Practical Treatment. Avoid contamination of food and feedstuffs. Keep out of the reach of children.

A committee of the National Academy of Sciences has stated that:

"There are no adequate data to show that these compounds are carcinogenic in humans, but because of their carcinogenicity in certain mouse strains and the extensive similarity of the carcinogenic action of chemicals in animals and in humans, the committee concluded that chlordane, heptachlor, and/or their metabolites may be carcinogenic in humans."

**Environmental Hazards**

The product is toxic to fish, birds, and other animals. Keep out of streams, ponds, or lakes. Do not contaminate water by cleaning of equipment or disposal of wastes. Apply this product only as specified on this label.

**Physical or Chemical Hazards**

**DO NOT USE, POUR, SPILL OR STORE NEAR HEAT OR OPEN FLAME**

**GENERAL INFORMATION ON THE USE OF THIS PRODUCT**

Chemicals for soil treatment are used to establish a barrier against termites. The chemical emulsion must be adequately dispersed in the soil to provide a barrier between the wood in the structure and the termite colonies in the soil.

It is necessary for the effective use of this product that the service technician be familiar with current control practices including trenching, rodding, sub-slab injection and low pressure spray applications. These techniques must be correctly employed to prevent or control infestations by subterranean termite species of *Reticulitermes*, *Zootermopsis*, *Nasutitermes* and *Coptotermes*. Choice of appropriate procedures should include consideration of such variable factors as the design of the structure, existence of air circulation in sub-floor crawl space, water table, soil type, soil compaction, grade conditions, and location and type of domestic water supplies. The biology and behavior of the termite species involved are important factors to be known as well as suspected location of the colony and severity of the infestation within the structure to be protected.

For advice concerning current control practices with relation to the specific local conditions, consult resources in structural pest control.

**SUBTERRANEAN TERMITES CONTROL**

**DIRECTIONS FOR USE**  
**ONLY FOR SALE TO AND USE AND STORAGE**  
**BY COMMERCIAL PEST CONTROL OPERATORS**

It is a violation of Federal law to use this product in a manner inconsistent with its labeling. This product may not be used against any pests not named on the label. Contamination of public and private water supplies must be avoided by following these precautions. Use anti-backflow equipment or procedures to prevent siphonage of pesticide back into water supplies. Do not treat soil beneath structures that contain cisterns or wells. Do not treat soil that is water saturated or frozen. Consult state and local specifications for recommended distances of treatment areas from wells, and refer to Federal Housing Administration Specifications for further guidance.

All non-essential wood and cellulose containing materials, including drop wood and form boards, should be removed from ground foundation walls, other basements, and porches. Effective termite control also includes elimination of termite access to moisture by recommending repair of faulty construction gaps, water plumbing.

**PRECONSTRUCTION SUBTERRANEAN TERMITES TREATMENT**

Effective preconstruction subterranean termite control requires the establishment of an unbroken vertical and/or horizontal chemical barrier between wood in the structure and the potential or existing termite colonies in the soil.

To meet F.H.A. termite proofing requirements, follow the latest edition of the Housing and Urban Development (H.U.D.) Minimum Property Standards.

Use a 0.5% water emulsion for subterranean termites other than *Coptotermes* spp. Mix 1 gallon of H-88 in 99 gallons of water to produce a 0.5% water emulsion.

Use a 1% water emulsion for *Coptotermes* spp. where necessary. Mix 2 gallons of H-88 in 98 gallons of water to produce a 1% water emulsion.

Do not apply to any area intended as a plenum air space.

After grading is completed and prior to the pouring of the slab, the structural steelwork, plumbing, or electrical conduits, etc., should be installed.

**Horizontal Barriers**

Where it is necessary to produce a horizontal barrier, apply the emulsion at the rate of 1 gallon per 10 square feet to fill dirt. If fill is washed gravel or other coarse material, apply at 1-1/2 gallons per 10 square feet. It is important that the emulsion reaches the soil substrate. Applications shall be made by a low-pressure spray for horizontal barriers over areas intended for covering floors, porches and other critical areas.

If concrete slabs cannot be poured over soil the same day it has been treated, a water-proof cover, such as polyethylene sheeting, should be placed over the soil. This is not necessary if foundation walls have been installed around the treated soil.

**Vertical Barriers**

Establish a vertical barrier in areas such as around the base of foundations, plumbing, back-filled soil against foundation walls and other critical areas.

To produce a vertical barrier, apply the emulsion at the rate of 4 gallons per 10 linear feet per foot of depth from grade to the top of the footing.

- Rodding and/or trenching applications should not be made below the top of the footing.
- Trench need not be wider than 6 inches.
- When rodding, it is important that emulsion reaches the footing. Rod holes should be spaced (about 1 foot) to provide a continuous barrier.
- Emulsion should be mixed with the soil as it is being replaced in the footing. Cover treated soil with a thin layer of untreated soil, or other suitable barrier such as polyethylene sheeting.

**Hollow Masonry Units of The Foundation Walls**

Hollow block foundations or voids of masonry should be treated to make a continuous chemical barrier in voids. Apply at the rate of 2 gallons of emulsion per 10 linear feet so it will reach the footing.

**Crawl Spaces**

For crawl spaces apply at the rate of 4 gallons of emulsion per 10 linear feet per foot of depth from grade to the top of the footing. Application may be made by rodding and/or trenching. Do not make an overall broadcast application in areas intended to be crawl spaces; applications must be made by rodding and/or trenching. Treat both sides of foundation and around all piers and pipes.

- Rod holes should be spaced (about 1 foot) to provide a continuous chemical barrier.

DRP

9 MAR 1984

300/116766  
17/10

Mr. John Bergman  
Walston Chemical Corporation  
361 E. Ohio Street  
Chicago, IL 60611

Dear Mr. Bergman:

Subject: Amendment - Graphics Change; Change Product Names  
Gold Crest C-100 Emulsifiable Concentrate  
EPA Registration No. 876-63  
Gold Crest S-69 Emulsifiable Concentrate  
EPA Registration No. 876-62  
Gold Crest Turfide Emulsifiable Concentrate Insecticide  
EPA Registration No. 876-233  
Your Application Dated February 6, 1984

The amendments referred to above, submitted in connection with registration under the Federal Insecticide, Fungicide, and Rodenticide Act (FIFRA), are acceptable. Stamped copies of the label are enclosed for your records.

Note that when revising the storage and disposal sections for compliance with FR Notice 83-3 that the two products containing heptachlor should bear the following pesticide disposal text:

Pesticide wastes are acutely hazardous. Improper disposal of excess pesticide, spray mixture, or rinseate is a violation of Federal law. If these wastes cannot be disposed of by use according to label instructions, contact your State Pesticide or Environmental Control Agency, or the Hazardous Waste representative at the nearest EPA Regional Office for guidance.

The registration records for each of the products listed below have been adjusted to show each appropriate new product name:

<u>EPA Registration No.</u>	<u>New Product Name</u>
876-63	Gold Crest C-100 Insecticide Emulsifiable Concentrate

CONCURRENCES							

876-85

-2-

EPA Registration No.

New Product Name

876-85

Gold Crest H-60 Insecticide  
Emulsifiable Concentrate

876-233

Gold Crest Termiticide Insecticide  
Emulsifiable Concentrate

Sincerely yours,

George T. LaRocca  
Product Manager (15)  
Insecticide-Rodenticide Branch  
Registration Division (TS-767)

Enclosure

ED:JEM:DCR-85488:LaRocca:pcn:Enron:557-2226:ED-27:3/7/84:Del:3/18/84