

# 8 Lb. Emulsifiable Chlordane

GALLONS

EPA Reg. No. 1339-74

UTION

ach Of Children

act with skin can cause toxic spray mist. In case of contact and water. Avoid contamination

NOTE:

on skin, wash promptly with

poonful mustard in tumbler of lan.

birds, and other wildlife. Keep Do not contaminate waetr by disposal of wastes. Apply this this label.

OR STORE NEAR HEAT OR

Destroy when empty.

side panels.

An emulsifiable concentrate containing 8 lbs. technical Chlordane per gallon for the control of termites.

#### ACTIVE INGREDIENTS:

*Technical Chlordane	73.0%
Petroleum Distillate	21.0%
INERT INGREDIENTS	6.0%
TOTAL	100.0%

\*Equivalent to 43.8% Octachloro-4, 7-Methanotetrahydroir- dane and 29.2% Related Compounds.

Seller warrants that the product conforms to its chemical description and is reasonably fit for the purpose stated on the label when used in accordance with directions under normal conditions of use, but neither this warranty nor any other warranty of merchantability or fitness for a particular purpose, express or implied, extends to the use of this product contrary to label instructions, or under abnormal conditions, or under conditions not reasonably foreseeable to seller, and buyer assumes the risk of any such use.

MANUFACTURED BY



MONROE, LOUISIANA Made in U.S.A.

### Preconstruction Treatment

#### SLAB-ON-GROUND CONSTRUCTION

(1) Apply an over-all treatment under entire surface of floor slab. Apply at the rate of 1 gallon per 10 square feet, except that if fill under slab is gravel or other coarse absorbent material, apply at the rate of 1½ gallons per 10 square feet.

(2) Under slab-on-ground porch floors and entrance platforms, apply an over-all treatment at the rate of 1 gallon per 10 square feet.

(3) Along both sides of foundation wall, along interior foundation walls, and around plumbing dig a narrow trench to a depth of 1 foot, but not below the top of the footing. Apply at the rate of 2 gallons per 5 linear feet of trench. The chemical should be mixed with the soil as it is being replaced in the trench.

(4) Treat all voids in hollow masonry units of the foundation at the rate of at least 1 gallon per 5 linear feet of wall. Apply the emulsion so as to reach the footing.

#### BUILDINGS WITH CRAWL SPACES

(1) Dig a narrow trench to the top of the footing along the inside of foundation walls, around piers, sewer pipes and conduits. Apply 2 gallons of emulsion per 5 linear feet of trench. The chemical should be mixed with the soil as it is being replaced in the trench.

(2) Dig a narrow trench to the top of the footing along the outside of the foundation wall. Apply 2 gallons of emulsion per 5 linear feet of trench per each foot of depth. A trench 3 feet deep would require 6 gallons per 5 linear feet. The chemical should be mixed with the soil as it is being replaced in the trench.

(3) Under attached porches, entrance platforms, utility entrances, and similar situations where slab or fill is at the

same grade level apply 1 gallon per 10 square feet of soil surface.

(4) Treat all voids in hollow masonry units of the foundation at the rate of at least 1 gallon per 5 linear feet of wall. Apply the emulsion so as to reach the footing.

#### BUILDINGS WITH BASEMENTS

(1) Apply an over-all treatment under the basement floorings, as well as under attached porches, entrance platforms, utility entrances, and similar situations where slab fill is at the grade level. Apply at the rate of 1 gallon per 10 square feet, except that if fill under slab is of washed gravel, cinders, or similar coarse material, increase the dosage by at least one-half. Where crawl spaces exist, treat as described in part (2) below.

(2) Dig a narrow trench to the top of the footing along the inside of foundation walls, around piers, sewer pipes and conduits. Apply 2 gallons of emulsion per 5 linear feet of trench. The chemical should be mixed with the soil as it is being replaced in the trench.

(3) Along the outside of foundation walls, dig a narrow trench, such trench to be dug no deeper than the top of the footings. If the trench is less than 15 inches in depth to the top of the footings, apply 1 gallon per 5 linear feet. Replace

the soil and apply another 1 gallon per 5 linear feet to the back fill. Cover the back fill with a thin layer of soil. If the trench is more than 15 inches in depth to the top of the footings, apply 2 gallons per 5 linear feet. Replace the soil and apply another 2 gallons per 5 linear feet to the

back fill. Cover the back fill with a thin layer of soil. A trench 30 inches deep is a maximum depth required along-side foundations where the top of the footings is greater than 30 inches deep. In lieu of trenching to a 30" depth, make the trench 12 to 15" deep and rod to footing, spacing the holes about 1 foot apart.

(4) Treat all voids in hollow masonry units of the foundation at the rate of 1 gallon per 5 linear feet of wall. Apply the emulsion so as to reach the footing.