



MASTER 2 ALDRIN

FOR TERMITES

Contains 2 Lbs. Per Gallon

CONTENTS BY WEIGHT

ACTIVE INGREDIENTS: *Aldrin 23.2%
INERT INGREDIENTS: 76.8%

TOTAL 100.00%

*22.0% Hexachlorohexahydro-endo, exo-dimethanonaphthalene and 1.2% related compounds.

DANGER

KEEP OUT OF REACH OF CHILDREN.

DIRECTIONS

TERMITE CONTROL: Specific Directions for Commercial Operators.

To control termites add 2 gallons Master Brand Termite Emulsifiable Concentrate to 95 gallons of water (0.5% Emulsion). Apply the resulting emulsion at the following rates:

(A) Buildings with crawl spaces—(1) Apply 2 gallons per 5 linear feet to critical areas only under the house, such as along the outside of foundation walls, around piers, sewer pipes, conduits, etc. Trench according to directions in part 2 below.

(2) Along the outside of foundation walls, dig a narrow trench, such trench to be dug no deeper than the top of the footings. If the trench is less than 15 inches in depth to the top of the footings, apply 1 gallon per 5 linear feet. Replace the soil and apply another 1 gallon per 5 linear feet to the back fill. Cover the back fill with a thin layer of soil. If the trench is more than 15 inches in depth to the top of the footings, apply 2 gallons per 5 linear feet. Replace the soil and apply another 2 gallons per 5 linear feet to the back fill. Cover the back fill with a thin layer of soil. A trench 30 inches deep is a maximum depth required alongside those foundations where the top of the footings is greater than 30 inches deep. In lieu of trenching to a 30 inch depth, make the trench 12 to 15 inches deep and rod to footing, spacing the holes about 1 foot apart.

(3) Apply one gallon per 10 square feet of soil surface under attached porches, entrance platforms, utility entrances and similar situations where slab or fill is at grade level. Where crawl spaces exist, treat as described in part (1) above.

(4) Treat all voids in hollow masonry units of the foundation at the rate of at least 1 gallon per 5 linear feet of wall. It is best to apply the chemical near the footing.

(B) Buildings with concrete slab on the ground. (1) Apply 1 gallon per 10 square feet as an over-all treatment under the slab as well as under the attached porches, entrance platforms, utility entrances and similar situations where slab or fill is at grade level. In case of washed gravel, cinders, or similar coarse material, increase the dosage by at least one-half.

(2) Apply 2 gallons per 5 linear feet to critical areas only around sewer pipes, conduits, etc. Trench as in part (3) below.

(3) Along the outside of foundation walls, dig a narrow trench no deeper than the top of the footings, but no deeper than 15 inches, unless the footing is much deeper in some places on account of the slope of the land, then treat as under (A) (2).

(4) Treat all voids in hollow masonry units of the foundation at the rate of at least 1 gallon per 5 linear feet of wall. It is best to apply the chemical near the footings.

(C) Buildings With Basements. (1) Apply one gallon per 10 square feet as an over all treatment under the basement flooring, as well as under attached porches,

entrance platforms, utility entrances and similar situations where slab fill is at the grade level. In case of washed gravel, cinders, or similar coarse material, increase the dosage by at least one-half. Where the crawl spaces exist, treat as described in part (2) below.

(2) Apply 2 gallons per 5 linear feet to critical areas only under the basement floorings, as well as porches and entrances having crawl spaces, such as along the inside of foundation walls, around sewer pipes, conduits, piers, etc. Trench according to directions in part (3) below.

(3) Along the outside of foundations walls, dig a narrow trench, such trench to be dug no deeper than the top of the footings. If the trench is less than 15 inches in depth to the top of the footings, apply 1 gallon per 5 linear feet. Replace the soil and apply another 1 gallon per 5 linear feet to the back fill. Cover the back fill with a thin layer of soil. If the trench is more than 15 inches in depth to the top of the footings, apply 2 gallons of chemical per 5 linear feet. Replace the soil and apply another 2 gallons per 5 linear feet to the back fill. Cover the back fill with a thin layer of soil. A trench 30 inches deep is a maximum depth required alongside foundations where the top of the footings is greater than 30 inches deep. In lieu of trenching to a 30" depth, make the trench 12 to 15" deep and rod to footing, spacing the holes about one foot apart.

(4) Treat all voids in hollow masonry units of the foundation at the rate of one gallon per 5 linear feet of wall. It is best to apply the chemical near the footing.

CAUTION

Do not apply or allow to drift to areas occupied by unprotected humans or beneficial animals. Highly toxic to fish and wildlife. Do not contaminate streams, lakes or ponds with the material. During commercial or prolonged exposure in spraying and unloading operations, wear clean, synthetic rubber gloves and a mask or respirator of a type passed by the U. S. Department of Agriculture for Aldrin protection. Use the product only for recommended purposes and at recommended dosages.

WARNING

Hazardous if swallowed, inhaled or absorbed through skin. Do not breathe dust or spray mix. Do not get in eyes, on skin or on clothing. Wash thoroughly with soap and water after handling and before eating or smoking. Wear clean clothing. In case of accidental spillage on person or clothing, immediately remove clothing and flush skin or eyes with plenty of water; for eyes, get medical attention. Keep away from heat and open flame.

NOTICE

Stevens Industries, Inc., warrants (its liability under any warranty or representation being limited to replacement of the product named on this label) that said product as sold by it consists of the ingredients specified, but makes no warranty or representation of any kind express or implied, including any warranty or representation regarding the effect or result of this product's use, whether or not the product is used in accordance with directions and accepts no responsibility whatsoever for injury to persons, loss or damage to property resulting from such use.

ACCEPTED

MAY 11 1965

UPP
FUR
E

Manufactured By

STEVENS INDUSTRIES, INC.

DAWSON, GEORGIA

U.S.D.A. Reg. No. 24,928