

DIRECTIONS FOR USE

It is a violation of Federal law to use this product in a manner inconsistent with its labeling.

Suspension must be shaken or stirred before use. Pour the recommended amount of THURICIDE 16B into the required volume of water in the spray tank. Agitate as necessary to maintain suspension. Do not allow diluted sprays to remain in the tank for more than 24 hours. THURICIDE 16B is formulated to provide desirable coverage and stickability on leaf surfaces. Additional adjuvants, spreaders, or stickers may be added but are not essential.

Ground Application:

Use adequate water to obtain good foliar

coverage. Wet foliage but do not allow excessive runoff. Apply the recommended per-acre rates of THURICIDE 16B with the following suggested amounts of water:

100 gallons with high gallonage hydraulic sprayers

10 gallons with mist blower

Aerial Application

Use a minimum of 20% water in the spray mix per acre. Use not less than one-half gallon of spray mix per acre. Best results are obtained when THURICIDE 16B is applied to dry foliage with a calibrated aircraft capable of obtaining droplet sizes below 300 microns and preferably in the range of 50-150 microns.

STORAGE AND DISPOSAL

STORAGE: Store in a cool place.

DISPOSAL: Thoroughly clean and rinse empty drum with water and remove labeling. Rinsate should be disposed of by burial.

NOTICE: Sandoz, Inc. makes no warranty, express or implied, including the warranties of merchantability and/or fitness for any particular purpose, concerning this material except those which are contained on this label.



ACTIVE INGREDIENTS: *Bacillus thuringiensis* Berliner, potency of 3,430 International Units (at least 5 million viable spores) per milligram.

INERT INGREDIENTS:

Equivalent to 4.0 billion International Units per quart.

KEEP OUT OF REACH OF CHILDREN

CAUTION

AVOID INHALATION OR CONTACT WITH EYES OR OPEN WOUNDS

NET
LOT



Sandoz, Inc.
Crop Protection
460 Camino Del Rio So.
San Diego, California 92108

EP
EP

Thuricide-16B

CONCENTRATE FOR AERIAL OR GROUND APPLICATION

msis Berliner potency of 3 430 International
milligram

0 69
99 31
100 00

OUT OF REACH OF CHILDREN

CAUTION

WITH EYES OR OPEN WOUNDS



Sandoz, Inc.
Crop Protection
480 Camino Del Rio So.
San Diego, California 92108

EPA Reg. No. 11273-11
EPA Est. No. 36299-CA-1

RECOMMENDATIONS Thorough coverage is essential when using THURICIDE 16B. Use the higher rates against very heavy worm infestations.

FOR SHADE TREES, ORNAMENTALS & FOREST

Pest	Qts. per Acre	DIRECTIONS FOR USE
Spring and Fall cankerworm	1-2	Apply when leaf expansion reaches 40% 50% as infestation warrants. If eggs hatch over a long period of time or if reinfestation occurs, spray about 14 days after first ap- plication.
Elm spanworm	1-2	
Tent caterpillars	1-2	
Gypsy moth	2-3	
Spruce budworms	1 1/2-3	Apply when most larvae are 3rd-4th instar. Also consider the opening of the bud cap to ensure foliage exposure.
Douglas fir tussock moth	1-2	Apply after eggs have hatched and early in- star larvae are feeding on exposed foliage.
Jack pine budworm	1-2	
Bagworm	1-2	
California oak moth	1-2	
Western tussock moth	1-2	
Fruit tree leafroller	1-2	
Mimosa webworm	1-2	
Redhumped caterpillar	1 1/2-2	
Fall webworm	1-2	

